



# **EDB Postgres™ Advanced Server Installation Guide**

**EDB Postgres™ Advanced Server 9.6**

**February 15, 2021**

EDB Postgres™ Advanced Server Installation Guide  
by EnterpriseDB® Corporation  
Copyright © 2009 - 2021 EnterpriseDB Corporation. All rights reserved.

EnterpriseDB Corporation, 34 Crosby Drive Suite 100, Bedford, MA 01730, USA  
**T** +1 781 357 3390 **F** +1 978 589 5701 **E** info@enterprisedb.com **www**.enterprisedb.com

# Table of Contents

1	Introduction.....	6
1.1	Typographical Conventions Used in this Guide.....	7
2	Requirements Overview.....	8
2.1	Supported Platforms.....	8
2.2	Supported Locales.....	8
2.3	RPM Installation Pre-requisites.....	9
3	Using a Package Manager to Install Advanced Server.....	10
3.1	Installing Advanced Server on a CentOS Host.....	11
3.2	Installing Advanced Server on a RHEL Host.....	12
3.3	Installing Advanced Server on a CentOS/RHEL 7 ppc64le Host.....	14
3.4	Installing a Package on SLES 12.....	16
3.5	Updating an RPM Installation.....	20
3.6	Installing Advanced Server on an Isolated Network.....	21
3.7	Configuring a Package Installation.....	23
3.7.1	Modifying the data Directory Location on CentOS or RedHat 7.x.....	23
3.7.2	Specifying initdb Options in the Service Configuration File.....	24
3.7.3	Creating a Database Cluster and Starting the Service.....	25
3.7.4	Starting Multiple Postmasters with Different Clusters.....	26
3.8	Advanced Server RPM Installers.....	27
4	Installing Advanced Server with the Interactive Installer.....	30
4.1	Graphical Installation Prerequisites.....	32
4.2	Locales Requiring Product Keys.....	34
4.3	Performing a Graphical Installation.....	36
4.3.1	Using the Graphical Installer with Windows.....	37
4.3.2	Using the Graphical Installer on a Linux System.....	56
4.4	Invoking the Installer from the Command Line.....	76
4.4.1	Performing a Text Mode Installation.....	77
4.4.2	Performing an Unattended Installation.....	89
4.4.3	Performing an Installation with Limited Privileges.....	92
4.4.4	Reference - Command Line Options.....	106
4.5	Using StackBuilder Plus.....	115
5	Managing an Advanced Server Installation.....	127
5.1	Starting and Stopping Advanced Server and Supporting Components.....	127
5.2	Controlling a Service on Linux.....	128
5.2.1	Controlling a Service on CentOS or RHEL 7.x.....	128
5.2.2	Using pg_ctl to Control Advanced Server.....	129
5.2.3	Using the edbstart and edbstop Utilities.....	131

5.2.4	Configuring Component Services to AutoStart at System Reboot .....	134
5.3	Controlling a Service on Windows .....	135
5.3.1	Controlling Server Startup Behavior on Windows .....	137
5.4	Using initdb to Create a Cluster .....	139
6	Configuring Advanced Server .....	141
6.1	Modifying the postgresql.conf File .....	142
6.2	Modifying the pg_hba.conf File .....	145
6.3	Setting Advanced Server Environment Variables .....	146
6.4	Connecting to Advanced Server .....	148
6.4.1	Connecting to an Oracle or MySQL Database .....	149
7	Advanced Server Supporting Components .....	150
7.1	EDB*Plus - Configuring an RPM Installation .....	150
7.2	Infinite Cache .....	152
7.3	Language Pack .....	155
7.4	Migration Toolkit - Configuring an RPM Installation .....	158
7.5	pgAgent .....	160
7.6	PgBouncer .....	161
7.7	pgPool-II .....	166
7.8	pgsnmpd .....	176
7.9	PL/Java .....	179
7.9.1	Installing PL/Java on Linux .....	179
7.9.2	Installing PL/Java on Windows .....	181
7.9.3	Using PL/Java .....	182
7.10	PL/Perl .....	184
7.11	PL/Python .....	185
7.12	PL/Tcl .....	187
7.13	PostGIS .....	188
7.13.1	Upgrading to PostGIS 2.3 .....	190
7.14	SQL Profiler .....	194
7.15	sslutils .....	196
8	Upgrading an Installation With pg_upgrade .....	198
8.1	Performing an Upgrade - Overview .....	199
8.1.1	Linking versus Copying .....	200
8.2	Invoking pg_upgrade .....	201
8.2.1	Command Line Options - Reference .....	203
8.3	Upgrading to Advanced Server 9.6 – Step-by-Step .....	206
8.4	pg_upgrade Troubleshooting .....	215
8.4.1	Upgrade Error - There seems to be a postmaster servicing the cluster .....	215
8.4.2	Upgrade Error - fe_sendauth: no password supplied .....	215

8.4.3	Upgrade Error - New cluster is not empty; exiting .....	215
8.4.4	Upgrade Error - Failed to load library .....	216
8.5	Reverting to the Old Cluster .....	216
8.6	Migration to Version 9.6 .....	217
9	Uninstalling Advanced Server .....	220
9.1	Uninstalling a RPM Package .....	220
9.1.1	Uninstalling a RPM Package with rpm .....	220
9.1.2	Uninstalling a RPM Package with yum .....	220
9.2	Using Advanced Server Uninstallers at the Command Line .....	222
9.3	Uninstalling Advanced Server on a Windows System .....	225

# 1 Introduction

The EDB Postgres Advanced Server Installation Guide is a comprehensive guide to installing EDB Postgres Advanced Server (Advanced Server). In this guide you will find detailed information about:

- Software prerequisites for Advanced Server 9.6
- Using a package manager to install and update Advanced Server and its supporting components or utilities
- Installation options available through the interactive Setup wizard on both Linux and Windows
- Managing an Advanced Server installation
- Configuring an Advanced Server installation
- Configuring Advanced Server supporting components
- Using `pg_upgrade` to upgrade from an earlier version of Advanced Server to Advanced Server 9.6
- Uninstalling Advanced Server and its components

## 1.1 *Typographical Conventions Used in this Guide*

Certain typographical conventions are used in this manual to clarify the meaning and usage of various commands, statements, programs, examples, etc. This section provides a summary of these conventions.

In the following descriptions, a *term* refers to any word or group of words that are language keywords, user-supplied values, literals, etc. A term's exact meaning depends upon the context in which it is used.

- *Italic font* introduces a new term, typically in the sentence that defines it for the first time.
- Fixed-width (mono-spaced) font is used for terms that must be given literally such as SQL commands, specific table and column names used in the examples, programming language keywords, etc. For example, `SELECT * FROM emp;`
- *Italic fixed-width font* is used for terms for which the user must substitute values in actual usage. For example, `DELETE FROM table_name;`
- A vertical pipe | denotes a choice between the terms on either side of the pipe. A vertical pipe is used to separate two or more alternative terms within square brackets (optional choices) or braces (one mandatory choice).
- Square brackets [ ] denote that one or none of the enclosed terms may be substituted. For example, [ a | b ] means choose one of “a” or “b” or neither of the two.
- Braces { } denote that exactly one of the enclosed alternatives must be specified. For example, { a | b } means exactly one of “a” or “b” must be specified.
- Ellipses ... denote that the preceding term may be repeated. For example, [ a | b ] ... means that you may have the sequence, “b a a b a”.

## 2 Requirements Overview

The following sections detail the supported platforms and installation requirements for EDB Postgres Advanced Server 9.6.

### 2.1 Supported Platforms

To review a list of supported platforms, visit the EnterpriseDB website at:

<https://www.enterprisedb.com/product-compatibility>

**Note:**

- The data directory of a production database should not be stored on an NFS file system.
- Advanced Server is no longer supported on RHEL/CentOS/OEL 6.x platforms. It is strongly recommended that EDB products running on these platforms be migrated to a supported platform.

### 2.2 Supported Locales

Advanced Server inherits support for many locales from PostgreSQL. While the installers have been used successfully in various locales, EnterpriseDB has explicitly tested and certified for the following locales:

Locale	Language
en_US	United States English
zh_HK	Traditional Chinese with Hong Kong SCS
zh_TW	Traditional Chinese for Taiwan
zh_CN	Simplified Chinese
ja_JP	Japanese
ko_KR	Korean

For more information about the locales supported by PostgreSQL, please see:

<https://www.postgresql.org/docs/current/static/locale.html>



## **2.3 RPM Installation Pre-requisites**

You can use an RPM package to install Advanced Server and its supporting components on a Linux host. Before installing the Advanced Server, you must:

### **Request Credentials for the EnterpriseDB Repository**

Before installing Advanced Server, you must have credentials that allow access to the EnterpriseDB repository. For information about requesting credentials, visit:

<https://info.enterprisedb.com/rs/069-ALB-339/images/Repository%20Access%2004-09-2019.pdf>

After receiving your repository credentials you can:

- Create the repository configuration file.
- Modify the file, providing your user name and password.
- Install Advanced Server and its supporting components.

## 3 Using a Package Manager to Install Advanced Server

You can use the yum package manager to install Advanced Server or Advanced Server supporting components. yum will attempt to satisfy package dependencies as it installs a package, but requires access to the Advanced Server repositories. If your system does not have access to a repository via the Internet, you can use RPM to install a package or create a local repository, but you may be required to manually satisfy package dependencies.

The Advanced Server meta installer RPM installs Advanced Server and its core components. You can use the meta installer for installation convenience, or pick and choose any sub-component that you need on a particular machine. Note that some sub-components require the installation of other Advanced Server component packages, while other packages may be installed individually. For a complete list of the RPM installers available for Advanced Server and its supporting components, see Section [3.8](#).

Installing the server package creates a database superuser named `enterprisedb`. The user is assigned a user ID (UID) and a group ID (GID) of 26. The user has no default password; use the `passwd` command to assign a password for the user. The default shell for the user is `bash`, and the user's home directory is `/var/lib/edb/as9.6`.

By default, Advanced Server logging is configured to write files to the `pg_log` subdirectory of the `data` directory, rotating the files each day and retaining one week of log entries. You can customize the logging behavior of the server by modifying the `postgresql.conf` file; for more information about modifying the `postgresql.conf` file, please see Section [6.1](#).

The RPM installers place Advanced Server components in the directories listed in the table below:

Component	Location
Executables	<code>/usr/edb/as9.6/bin</code>
Libraries	<code>/usr/edb/as9.6/lib</code>
Cluster configuration files	<code>/etc/edb/as9.6</code>
Documentation	<code>/usr/edb/as9.6/share/doc</code>
Contrib	<code>/usr/edb/as9.6/share/contrib</code>
Data	<code>/var/lib/edb/as9.6/data</code>
Logs	<code>/var/log/as9.6</code>
Lock files	<code>/var/lock/as9.6</code>
Log rotation file	<code>/etc/logrotate.d/as9.6</code>
Sudo configuration file	<code>/etc/sudoers.d/as9.6</code>
Binary to access VIP without sudo	<code>/usr/edb/as9.6/bin/secure</code>
Backup area	<code>/var/lib/edb/as9.6/backups</code>
Templates	<code>/usr/edb/as9.6/share</code>
Procedural Languages	<code>/usr/edb/as9.6/lib</code> or <code>/usr/edb/as-9.6/lib64</code>

Component	Location
Development Headers	/usr/edb/as9.6/include
Shared data	/usr/edb/as9.6/share
Regression tests	/usr/edb/as9.6/lib/pgxs/src/test/regress
SGML Documentation	/usr/edb/as9.6/share/doc

The file locations are Linux Standard Base (LSB) compliant.

### 3.1 Installing Advanced Server on a CentOS Host

You can use an RPM package to install Advanced Server on a CentOS host.

- To install the repository configuration file, assume superuser privileges and invoke the following platform-specific command:

On CentOS 7:

```
yum -y install https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

- Replace the `USERNAME:PASSWORD` in the following command with the username and password of a registered EnterpriseDB user:

```
sed -i "s@<username>:<password>@USERNAME:PASSWORD@" /etc/yum.repos.d/edb.repo
```

- Before installing Advanced Server, you must install the `epel-release` package:

On CentOS 7:

```
yum -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
```

The repository configuration file is named `edb.repo`. The file resides in `/etc/yum.repos.d`.

After creating the `edb.repo` file, use your choice of editor to ensure that the value of the `enabled` parameter is `1`, and replace the `username` and `password` placeholders in the `baseurl` specification with a registered EnterpriseDB username and password.

```
[edb]
name=EnterpriseDB RPMs $releasever - $basearch
baseurl=https://<username>:<password>@yum.enterprisedb.com/edb/re
dhat/rhel-$releasever-$basearch
enabled=1
```

```
gpgcheck=1
gpgkey=file:///etc/pki/rpm-gpg/ENTERPRISEDB-GPG-KEY
```

After saving your changes to the configuration file, you can use `yum install` command to install Advanced Server. For example, to install the server and its core components, use the command:

- On CentOS 7:

```
yum -y install edb-as96-server
```

When you install an RPM package that is signed by a source that is not recognized by your system, yum may ask for your permission to import the key to your local server. If prompted, and you are satisfied that the packages come from a trustworthy source, enter a `y`, and press `Return` to continue.

After installing Advanced Server, you must configure the installation; see Section [3.7](#), *Configuring an Advanced Server Installation*, for details.

During the installation, yum may encounter a dependency that it cannot resolve. If it does, it will provide a list of the required dependencies that you must manually resolve.

## 3.2 Installing Advanced Server on a RHEL Host

You can use an RPM package to install Advanced Server on a RHEL host.

- To install the repository configuration file, assume superuser privileges and invoke the following platform-specific command:

On RHEL 7:

```
yum -y install https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

- Replace the `USERNAME:PASSWORD` in the following command with the username and password of a registered EnterpriseDB user:

```
sed -i "s@<username>:<password>@USERNAME:PASSWORD@"
/etc/yum.repos.d/edb.repo
```

- Before installing Advanced Server, you must install the `epel-release` package:

On RHEL 7:

```
yum -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
```

- Enable the repository:

On RHEL7, enable the `optional`, `extras`, and `HA` repositories to satisfy package dependencies:

```
subscription-manager repos --enable "rhel-*-optional-rpms" --enable "rhel-*-extras-rpms" --enable "rhel-ha-for-rhel-*-server-rpms"
```

The repository configuration file is named `edb.repo`. The file resides in `/etc/yum.repos.d`.

After creating the `edb.repo` file, use your choice of editor to ensure that the value of the `enabled` parameter is `1`, and replace the `username` and `password` placeholders in the `baseurl` specification with a registered EnterpriseDB username and password.

```
[edb]
name=EnterpriseDB RPMs $releasever - $basearch
baseurl=https://<username>:<password>@yum.enterprisedb.com/edb/re
dhat/rhel-$releasever-$basearch
enabled=1
gpgcheck=1
gpgkey=file:///etc/pki/rpm-gpg/ENTERPRISEDB-GPG-KEY
```

After saving your changes to the configuration file, you can use `yum install` command to install Advanced Server. For example, to install the server and its core components, use the command:

- On RHEL 7:

```
yum -y install edb-as96-server
```

When you install an RPM package that is signed by a source that is not recognized by your system, `yum` may ask for your permission to import the key to your local server. If prompted, and you are satisfied that the packages come from a trustworthy source, enter a `y`, and press `Return` to continue.

After installing Advanced Server, you must configure the installation; see Section [3.7](#), *Configuring an Advanced Server Installation*, for details.

During the installation, `yum` may encounter a dependency that it cannot resolve. If it does, it will provide a list of the required dependencies that you must manually resolve.

### 3.3 Installing Advanced Server on a CentOS/RHEL 7 ppc64le Host

You can use an RPM package to install Advanced Server on a CentOS or RHEL 7 ppc64le host.

- To install Advance Toolchain repository:

On CentOS or RHEL 7 ppc64le:

```
rpm --import
https://public.dhe.ibm.com/software/server/POWER/Linux/toolchain/at/redhat/RHEL7/gpg-pubkey-6976a827-5164221b
```

The repository configuration file is named `advance-toolchain.repo`. The file resides in `/etc/yum.repos.d`.

- After creating the `advance-toolchain.repo` file, use your choice of editor to set the value of the `enabled` parameter to `1`, and replace the `username` and `password` placeholders in the `baseurl` specification with a registered EnterpriseDB username and password.

```
[advance-toolchain]
name=Advance Toolchain IBM FTP
baseurl=https://public.dhe.ibm.com/software/server/POWER/Linux/toolchain/at/redhat/RHEL7
failovermethod=priority
enabled=1
gpgcheck=1
gpgkey=ftp://public.dhe.ibm.com/software/server/POWER/Linux/toolchain/at/redhat/RHELX/gpg-pubkey-6976a827-5164221b
```

- To install the repository configuration file, assume superuser privileges and invoke the following platform-specific command:

On CentOS or RHEL 7 ppc64le:

```
yum -y install https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

- Replace the `USERNAME:PASSWORD` in the following command with the username and password of a registered EnterpriseDB user:

```
sed -i "s@<username>:<password>@USERNAME:PASSWORD@"
/etc/yum.repos.d/edb.repo
```

- Before installing Advanced Server, you must install the `epel-release` package:

On CentOS or RHEL 7 ppc64le:

```
yum -y install http://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
```

- On RHEL 7, enable required repositories; enable the optional, extras, and HA repositories to satisfy package dependencies:

```
subscription-manager repos --enable "rhel-*-optional-rpms" --enable "rhel-*-extras-rpms" --enable "rhel-ha-for-rhel-*-server-rpms"
```

The repository configuration file is named `edb.repo`. The file resides in `/etc/yum.repos.d`.

After creating the `edb.repo` file, use your choice of editor to ensure that the value of the `enabled` parameter is `1`, and replace the `username` and `password` placeholders in the `baseurl` specification with a registered EnterpriseDB username and password.

```
[edb]
name=EnterpriseDB RPMs $releasever - $basearch
baseurl=https://<username>:<password>@yum.enterprisedb.com/edb/re
dhat/rhel-$releasever-$basearch
enabled=1
gpgcheck=1
gpgkey=file:///etc/pki/rpm-gpg/ENTERPRISEDB-GPG-KEY
```

After saving your changes to the configuration file, you can use `yum install` command to install Advanced Server. For example, to install the server and its core components, use the command:

- On CentOS or RHEL 7 ppc64le:

```
yum -y install edb-as96-server
```

When you install an RPM package that is signed by a source that is not recognized by your system, `yum` may ask for your permission to import the key to your local server. If prompted, and you are satisfied that the packages come from a trustworthy source, enter a `y`, and press `Return` to continue.

After installing Advanced Server, you must configure the installation; see Section [3.7](#), *Configuring an Advanced Server Installation*, for details.

During the installation, `yum` may encounter a dependency that it cannot resolve. If it does, it will provide a list of the required dependencies that you must manually resolve.

### 3.4 Installing a Package on SLES 12

You can use the zypper package manager to install Advanced Server or Advanced Server supporting components on an SLES 12 host. zypper will attempt to satisfy package dependencies as it installs a package, but some components require access to specific repositories that are not hosted at EnterpriseDB.

To add Advanced Server or supporting components, use the following commands to add EnterpriseDB repository configuration files to your SLES host:

```
zypper addrepo https://zypp.enterprisedb.com/suse/epas96-
sles.repo
zypper addrepo https://zypp.enterprisedb.com/suse/epas-sles-
tools.repo
zypper addrepo https://zypp.enterprisedb.com/suse/epas-sles-
dependencies.repo
```

Each command creates a repository configuration file in the `/etc/zypp/repos.d` directory. The files are named:

- `edbas96suse.repo`
- `edbasdependencies.repo`
- `edbastools.repo`

After creating the repository configuration files, use the `zypper refresh` command to refresh the metadata on your SLES host to include the EnterpriseDB repositories:

```
/etc/zypp/repos.d # zypper refresh
Repository 'SLES12-12-0' is up to date.
Repository 'SLES12-Pool' is up to date.
Repository 'SLES12-Updates' is up to date.
Retrieving repository 'EDB Postgres Advanced Server 9.6 12 -
x86_64' metadata -----[\\]

Authentication required for
'https://zypp.enterprisedb.com/9.6/suse/suse-12-x86_64'
User Name:
Password:

Retrieving repository 'EDB Postgres Advanced Server 9.6 12 -
x86_64' metadata.....[done]
Building repository 'EDB Postgres Advanced Server 9.6 12 -
x86_64' cache.....[done]
All repositories have been refreshed.
...
```



When prompted for a `User Name` and `Password`, provide your connection credentials for the EnterpriseDB repository. If you need credentials, contact EnterpriseDB at:

<https://www.enterprisedb.com/general-inquiry-form>

Before installing EDB Postgres Advanced Server or supporting components, you must also add SUSEConnect and the SUSE Package Hub extension to the SLES host, and register the host with SUSE, allowing access to SUSE repositories. Use the commands:

```
zypper install SUSEConnect
SUSEConnect -p PackageHub/12/x86_64
SUSEConnect -p sle-sdk/12/x86_64
```

For detailed information about registering a SUSE host, visit:

<https://www.suse.com/support/kb/doc/?id=7016626>

The following sections provide information about the specific repositories that are not hosted by EnterpriseDB, but that provide software that satisfies dependencies for each listed component. Please note that after adding repository access, you should use the `zypper refresh` command to process the repository content:

```
zypper refresh
```

### ***Java Components:***

Please note that only OpenJDK (version 1.8) is supported on SLES hosts of Java components. Before using an RPM installer to add Advanced Server or a supporting component that requires Java, use `zypper` to add supporting repository locations to your system.

Use the commands:

```
zypper addrepo
http://download.opensuse.org/repositories/Java:/Factory/SLE_12_SP
2/Java:Factory.repo
```

```
zypper refresh
```

Then you can use the `zypper install` command to install Advanced Server or supporting components. For example, to install the server and its core components, invoke the command:

```
zypper install edb-as96
```

### ***Slony:***

If you are using a package to add Slony to an SLES host, please note that you must add access to the Perl repository:

For SLES 12 SP2:

```
zypper addrepo
http://download.opensuse.org/repositories/devel:languages:perl/SLE_12_SP2/devel:languages:perl.repo
```

For SLES 12 SP3:

```
zypper addrepo
http://download.opensuse.org/repositories/devel:languages:perl/SLE_12_SP3/devel:languages:perl.repo
```

Then:

```
zypper refresh
```

### ***PostGIS:***

When using an RPM package to add PostGIS to an SLES host, you must add the following repository:

```
zypper addrepo
"http://download.opensuse.org/repositories/server:/Kolab:/3.3/SLE_12/server:Kolab:3.3.repo"
```

### ***PEM Agent or pgAgent:***

When adding the PEM agent or pgAgent packages to an SLES host, please note that you must add access to the wxWidgets repository:

For SLES 12 SP2:

```
SUSEConnect -p sle-module-legacy/12/x86_64
SUSEConnect -p sle-sdk/12/x86_64
zypper addrepo
http://download.opensuse.org/repositories/X11:/wxWidgets/SLE_12_SP2/X11:wxWidgets.repo
```

For SLES 12 SP3:

```
SUSEConnect -p sle-module-legacy/12/x86_64
SUSEConnect -p sle-sdk/12/x86_64
zypper addrepo
http://download.opensuse.org/repositories/X11:/wxWidgets/SLE_12_SP3/X11:wxWidgets.repo
```

Then:

```
zypper refresh
```

***BART:***

When installing BART on an SLES host, please note that you must add the SUSE SDK as well as the Archiving repository:

```
SUSEConnect -p sle-sdk/12/x86_64
```

```
zypper addrepo  
https://download.opensuse.org/repositories/Archiving/SLE_12_SP3/Archiving.repo
```

```
zypper refresh
```

***Updating Components on a SLES Host:***

To update components installed with zypper, use the `zypper update` command.

### 3.5 Updating an RPM Installation

If you have an existing Advanced Server RPM installation, you can use `yum` to upgrade your repository configuration file and update to a more recent product version. To update the `edb.repo` file, assume superuser privileges and enter:

- On RHEL or CentOS 7:

```
yum upgrade edb-repo
```

`yum` will update the `edb.repo` file to enable access to the current EDB repository, configured to connect with the credentials specified in your `edb.repo` file. Then, you can use `yum` to upgrade all packages whose names include the expression `edb`:

- On RHEL or CentOS 7:

```
yum upgrade edb*
```

Please note that the `yum upgrade` command will only perform an update between minor releases; to update between major releases, you must use `pg_upgrade`.

### 3.6 Installing Advanced Server on an Isolated Network

You can create a local yum repository to act as a host for the Advanced Server RPM packages if the server on which you wish to install Advanced Server (or supporting components) cannot directly access the EnterpriseDB repository. Please note that this is a high-level listing of the steps requires; you will need to modify the process for your individual network.

To create and use a local repository, you must:

- Use yum to install the `yum-utils` and `createrepo` packages:

On RHEL or CentOS 7:

```
yum install yum-utils
yum install createrepo
```

- Create a directory in which to store the repository:

```
mkdir /srv/repos
```

- Copy the RPM installation packages to your local network repository. You can download the individual RPM files from:

[yum.enterprisedb.com](http://yum.enterprisedb.com)

- Sync the RPM packages and create the repository.

```
reposync -r edbas96 -p /srv/repos
createrepo /srv/repos
```

- Install your preferred webserver on the host that will act as your local repository, and ensure that the repository directory is accessible to the other servers on your network. For example, you might install `lighttpd`:

```
yum install lighttpd
```

- If you are using `lighttpd`, you must provide a configuration file that identifies the location of the repository on your local network. For example, the configuration file might contain:

```
$HTTP["host"] == "yum.domain.com"{
    server.document-root = "/srv/repos"
    server.errorlog="/var/log/lighttpd/yum_error.log"
    accesslog.filename =
"/var/log/lighttpd/yum_access.log"}
```

For detailed information about installing, configuring and using lighttpd, visit the official project site at:

<http://redmine.lighttpd.net/projects/1/wiki/Docs>

- On each isolated database server, configure yum to pull updates from the mirrored repository on your local network. For example, you might create a file called `/etc/yum.repos.d/edb-repo` with connection information that specifies:

```
[edbas96]
name=EnterpriseDB Advanced Server 9.6
baseurl=http://yum.domain.com/edbas96
enabled=1
gpgcheck=0
```

After specifying the location and connection information for your local repository, you can use yum commands to install Advanced Server and its supporting components on the isolated servers. For example:

```
yum -y install edb-as96-server
```

For more information about creating a local repository, visit:

<http://yum.baseurl.org/>

## 3.7 Configuring a Package Installation

The packages that install the database server component create a unit file on version 7.x hosts and service startup scripts.

### 3.7.1 Modifying the data Directory Location on CentOS or RedHat 7.x

On a CentOS or RedHat version 7.x host, the unit file is named `edb-as-9.6.service` and resides in `/usr/lib/systemd/system`. The unit file contains references to the location of the Advanced Server data directory. You should avoid making any modifications directly to the unit file because it may be overwritten during package upgrades.

By default, data files reside under `/var/lib/edb/as9.6/data` directory. To use a data directory that resides in a non-default location, create a copy of the unit file under the `/etc` directory:

```
cp /usr/lib/systemd/system/edb-as-9.6.service
   /etc/systemd/system/
```

After copying the unit file to the new location, modify the service file (`/etc/systemd/system/edb-as-9.6.service`) with your editor of choice, correcting any required paths.

Then, use the following command to reload `systemd`, updating the modified service scripts:

```
systemctl daemon-reload
```

Then, start the Advanced Server service with the following command:

```
systemctl start edb-as-9.6
```

### 3.7.2 Specifying initdb Options in the Service Configuration File

By default, the `INITDBOPTS` variable is commented out in the service configuration file; unless modified, when you run the service startup script, the new cluster will be created in a mode compatible with Oracle databases. Clusters created in this mode will contain a database named `edb`, and have a database superuser named `enterprisedb`.

To create a new cluster in PostgreSQL mode, remove the pound sign (`#`) in front of the `INITDBOPTS` variable, enabling the `--no-redwood-compat` option. Clusters created in PostgreSQL mode will contain a database named `postgres`, and have a database superuser named `postgres`.

You may also specify multiple `initdb` options. For example, the following statement:

```
INITDBOPTS="--no-redwood-compat -U alice --locale=en_US.UTF-8"
```

Creates a database cluster (without compatibility features for Oracle) that contains a database named `postgres` that is owned by a user named `alice`; the cluster uses UTF-8 encoding.

For more information about creating a custom cluster with `initdb`, see [Section 5.4](#).



### 3.7.3 Creating a Database Cluster and Starting the Service

After specifying any options in the service configuration file, you must create the database cluster and start the service; these steps are platform specific.

#### *On RHEL or CentOS 7.x*

To invoke `initdb` on a RHEL or CentOS 7.x system, with the options specified in the service configuration file, assume the identity of the operating system superuser:

```
su - root
```

Then, invoke `initdb`:

```
/usr/edb/as9.6/bin/edb-as-96-setup initdb
```

After creating the cluster, use `systemctl` to start, stop, or restart the service:

```
systemctl { start | stop | restart } edb-as-9.6
```

### 3.7.4 Starting Multiple Postmasters with Different Clusters

It is possible to use multiple postmasters, each with its own database cluster. The following sections describe how to set up an additional Advanced Server instance with its database cluster.

#### *On RHEL or CentOS 7.x*

The `edb-as96-server-core` RPM contains a unit file that is used to start the Advanced Server instance. The current version of this script has the logic to be able to start multiple postmasters, with different data areas, listening on different ports, etc. To use this functionality requires `root` access.

As an example, a secondary Advanced Server instance referred to as `secondary` is created by the following steps:

- Copy the default unit file with the new name. As noted at the top of the unit file, all modifications must be under `/etc`. Be sure to pick a name not already used in `/etc/systemd/system`.

```
cp /usr/lib/systemd/system/edb-as-9.6.service
   /etc/systemd/system/secondary-edb-as-9.6.service
```

- Edit this file and change `PGDATA` to point to the new data directory that you will create the cluster against.
- Create the target `PGDATA` with user `enterprisedb`.
- Run `initdb` using the provided setup script:

```
/usr/edb/as9.6/bin/edb-as-96-setup initdb secondary-
edb-as-9.6
```

- Edit the `postgresql.conf` file to change the port, address, TCP/IP settings, etc.
- Make sure that new cluster runs after a reboot:

```
systemctl enable secondary-edb-as-9.6
```

- Start the second cluster with the following command:

```
systemctl start secondary-edb-as-9.6
```

### 3.8 Advanced Server RPM Installers

The tables that follow list the packages that are available from EnterpriseDB. Please note that you can also use the `yum search` command to access a list of the packages that are currently available from your configured repository. To use the `yum search` command, open a command line, assume root privileges, and enter:

```
yum search package
```

Where *package* is the search term that specifies the name (or partial name) of a package. The repository search will return a list of available packages that include the specified search term.

The following table lists the packages that are stored in the AS 96 repository and the corresponding software installed by those packages:

Package Name	Package Installs
edb-as96	The Meta Installer installs Advanced Server and its core supporting components. This package installs: Database server Client programs (edb-psql, pg_dump, pg_restore, and other client utilities) Community contributed modules and documentation ecpg/ecpgPlus EDB*Plus Index Advisor pgAgent pgsnmpd PL Debugger PL/Java PL/Perl PL/Python PL/Tcl Slony SQL Profiler SQL Protect sslutils Supporting library files
edb-as96-server	This package contains an Advanced Server meta installer that installs core components of the database server.
edb-as96-server-client	The <code>edb-as96-server-client</code> package contains client programs and utilities that you can use to access and manage Advanced Server.
edb-as96-server-contrib	The <code>edb-as96-contrib</code> package installs contributed tools and utilities that are distributed with Advanced Server. Files for these modules are installed in: Documentation: <code>/usr/edb/as9.6/share/doc</code> Loadable modules: <code>/usr/edb/as9.6/lib</code> Binaries: <code>/usr/edb/as9.6/bin</code>
edb-as96-server-core	The <code>edb-as96-server-core</code> package includes the programs

## EDB Postgres Advanced Server Installation Guide

Package Name	Package Installs
	needed to create the core functionality behind the Advanced Server database.
edb-as96-server-devel	The <code>edb-as96-server-devel</code> package contains the header files and libraries needed to compile C or C++ applications that directly interact with an Advanced Server server and the <code>ecpg</code> or <code>ecpgPlus C</code> preprocessor.
edb-as96-server-docs	The <code>edb-as96-server-docs</code> package installs the SGML source for the PostgreSQL documentation, as well as the documentation in HTML and PDF format.
edb-as96-server-indexadvisor	This package installs Advanced Server's Index Advisor feature. The Index Advisor utility helps determine which columns you should index to improve performance in a given workload.
edb-as96-server-libs	The <code>edb-as96-server-libs</code> package provides the essential shared libraries for any Advanced Server client program or interface.
edb-as96-server-pldebugger	This package implements an API for debugging PL/pgSQL functions on Advanced Server.
edb-as96-server-plperl	The <code>edb-as96-server-plperl</code> package installs the PL/Perl procedural language for Advanced Server. Please note that the <code>edb-as96-server-plperl</code> package is dependent on the platform-supplied version of Perl.
edb-as96-server-plpython	The <code>edb-as96-server-plpython</code> package installs the PL/Python procedural language for Advanced Server. Please note that the <code>edb-as96-server-plpython</code> package is dependent on the platform-supplied version of Python.
edb-as96-server-pltcl	The <code>edb-as96-pltcl</code> package installs the PL/Tcl procedural language for Advanced Server. Please note that the <code>edb-as96-pltcl</code> package is dependent on the platform-supplied version of TCL.
edb-as96-server-sqlprofiler	This package installs Advanced Server's SQL Profiler feature. SQL Profiler helps identify and optimize SQL code.
edb-as96-server-sqlprotect	This package installs Advanced Server's SQL Protect feature. SQL Protect provides protection against SQL injection attacks.
edb-as96-server-sslutils	This package installs functionality that provides SSL support.
edb-as96-edbplus	The <code>edb-edbplus</code> package contains the files required to install the EDB*Plus command line client. EDB*Plus commands are compatible with Oracle's SQL*Plus.
edb-as96-pgagent	This package installs pgAgent; pgAgent is a job scheduler for Advanced Server. Before installing this package, you must install EPEL.
edb-icache	This package installs InfiniteCache.
edb-icache-devel	This is a supporting package for InfiniteCache.
edb-as96-pgsnmpd	SNMP (Simple Network Management Protocol) is a protocol that allows you to supervise an apparatus connected to the network.
edb-as96-pljava	This package installs PL/Java, providing access to Java stored procedures, triggers and functions via the JDBC interface.
edb-as96-pgpool35-extensions	This package creates pgPool extensions required by the server.
edb-as96-slony-replication	This package contains the meta installer for Slony replication and documentation. Slony facilitates primary-standby replication, and is suited for large databases with a limited number of standbys.
edb-as96-slony-replication-core	This package contains the files required to install Slony replication. Slony facilitates primary-standby replication, and is suited for large databases with a limited number of standby systems.

Package Name	Package Installs
edb-as96-slony-replication-docs	This package contains the Slony project documentation (in pdf form).
edb-as96-slony-replication-tools	This package contains the Slony altp Perl tools and utilities that are useful when deploying Slony replication environments. Before installing this package, you must install EPEL.
edb-as96-postgis	The <code>edb-as96-postgis</code> package includes files used to add PostGIS functionality to Advanced Server
edb-as96-postgis-core	The <code>edb-as96-postgis-core</code> package includes PostGIS supporting files.
edb-as96-postgis-docs	The <code>edb-as96-postgis-docs</code> package provides PostGIS documentation files.
libevent-edb libiconv-edb libicu-edb	These packages contain supporting library files.

The following table lists the packages for Advanced Server 9.6 supporting components:

Package Name	Package Installs
edb-pgpool35	This package contains the pgPool-II meta installer. pgPool provides connection pooling for Advanced Server installations.
edb-pgpool35-devel	This package contains the pgPool-II headers and libraries.
edb-jdbc	The <code>edb-jdbc</code> package includes the .jar files needed for Java programs to access an Advanced Server database.
edb-migrationtoolkit	The <code>edb-migrationtoolkit</code> package installs Migration Toolkit, facilitating migration to an Advanced Server database from Oracle, PostgreSQL, MySQL, Sybase and SQL Server. Migration Toolkit requires Java (version 7 or 8), or OpenJDK (version 1.7 or 1.8).
edb-oci	The <code>edb-oci</code> package installs the EnterpriseDB Open Client library, allowing applications that use the Oracle Call Interface API to connect to an Advanced Server database.
edb-oci-devel	This package installs the OCI include files; install this package if you are developing C/C++ applications that require these files.
edb-odbc	This package installs the driver needed for applications to access an Advanced Server system via ODBC.
edb-odbc-devel	This package installs the ODBC include files; install this package if you are developing C/C++ applications that require these files.
edb-pgbouncer17	This package contains PgBouncer (a lightweight connection pooler). This package requires the libevent package.
edb-xdb	This package contains the xDB meta installer; xDB provides asynchronous cross-database replication. For more information, visit <a href="http://www.enterprisedb.com/faq-xdb-multi-master">http://www.enterprisedb.com/faq-xdb-multi-master</a>
edb-xdb-console	This package provides support for xDB.
edb-xdb-libs	This package provides support for xDB.
edb-xdb-publisher	This package provides support for xDB.
edb-xdb-subscriber	This package provides support for xDB.

Please Note: The available packages are subject to change.

## 4 Installing Advanced Server with the Interactive Installer

The Advanced Server installer is available from the EnterpriseDB website at:

<http://www.enterprisedb.com/downloads/postgres-postgresql-downloads>

After navigating to the `Software Downloads` page, choose the Advanced Server installation that corresponds to your platform. After selecting a download, you will be invited to register as an Advanced Server user. Enter your current EnterpriseDB login information, or complete an online registration form to start the download.

When the download completes, extract files using your system-specific file extractor.

You can use the extracted installer in different installation modes to perform an Advanced Server installation:

- For information about using the extracted files to perform a graphical installation on Windows, See Section [4.3.1](#).
- For information about performing a graphical installation on Linux, see Section [4.3.2](#).
- For information about using the installer to perform a command line installation, see Section [4.4](#).
- For information about performing an unattended installation, see Section [4.4.2](#).
- For information about performing an installation with limited privileges, see Section [4.4.3](#).
- For information about the command line options you can use when invoking the installer, see Section [4.4.4](#).

During the installation process, the Advanced Server installer program copies a number of temporary files to the location specified by the `TEMP` or `TMP` environment variable (on Windows), or to the `/tmp` directory (on Linux). You can optionally specify an alternate location for the installer to place the temporary files by modifying or creating the `TEMP` environment variable.

If invoking the installer from the command line, you can set the value of the variable on the command line:

On Windows, use the command:

```
SET TMP=temp_file_location
```

On Linux, use the command:

```
export TEMP=temp_file_location
```

Where `temp_file_location` specifies the alternate location for the temporary files.

**Please Note:** If you are invoking the installer to perform a system upgrade, the installer will preserve the configuration options specified during the previous installation.

## 4.1 Graphical Installation Prerequisites

### User Privileges

Before invoking the installer on a Linux system, you must have superuser privileges to perform an Advanced Server installation. To perform an Advanced Server installation on a Windows system, you must have administrator privileges. If you are installing Advanced Server into a Windows system that is configured with `User Account Control` enabled, you can assume sufficient privileges to invoke the graphical installer by right clicking on the name of the installer and selecting `Run as administrator` from the context menu. When prompted, enter an administrator password to continue (see Figure 4.1).




Figure 4.1 -The User Account Control window.

### Linux-specific Software Requirements

You must install `xterm`, `konsole`, or `gnome-terminal` before executing any console-based program installed by the Advanced Server installer. Without a console program, you will not be able to access Advanced Server configuration files through menu selections.

Before invoking the StackBuilder Plus utility on a Linux system, you must install the `redhat-lsb` package. To install the package, open a terminal window, assume superuser privileges, and enter:

```
# yum install redhat-lsb
```

For more information about using StackBuilder Plus, see Section [4.5](#).



## SELinux Permissions

Before invoking the installer on a system that is running SELinux, you must set SELinux to `permissive` mode.

The following example works on Redhat Enterprise Linux, Fedora Core or CentOS distributions. Use comparable commands that are compatible with your Linux distribution to set SELinux to `permissive` mode during installation and return it to `enforcing` mode when installation is complete.

Before installing Advanced Server, set SELinux to `permissive` mode with the command:

```
# setenforce Permissive
```

When the installation is complete, return SELinux to `enforcing` mode with the command:

```
# setenforce Enforcing
```

## Windows-specific Software Requirements

Be sure to apply Windows operating system updates before invoking the Advanced Server installer. If (during the installation process) the installer encounters errors, exit the installation, and ensure that your version of Windows is up-to-date before restarting the installer.

## Migration Toolkit or EDB\*Plus Installation Prerequisites

Before using the Advanced Server installer to install Migration Toolkit or EDB\*Plus, you must first install Java (version 7 or 8) or OpenJDK (version 1.7 or 1.8). On a Linux system, you can use the yum package manager to install Java. Open a terminal window, assume superuser privileges, and enter:

```
# yum install java-version
```

Follow the onscreen instructions to complete the installation.

If you are using Windows, Java installers and instructions are available online at:

<http://www.java.com/en/download/manual.jsp>


## 4.2 Locales Requiring Product Keys

The Advanced Server 9.6 installer will request a product key before completing an installation into a host system using one of the locales listed in the table below. Product keys are available from your local Advanced Server distributor.

**Note:** The product key applies only to the Advanced Server installation program. The Advanced Server database program has no built-in limitations or expiration features that require a product key or any other activation technique.

Locale	Locale Identifier
Traditional Chinese with Hong Kong SCS	zh_HK
Traditional Chinese for Taiwan	zh_TW
Simplified Chinese	zh_CN
Japanese	ja_JP
Korean	ko_KR
Argentina - Spanish	es_ar
Belize - English	en_bz
Brazil - Portuguese	pt_br
Bolivia - Spanish	es_bo
Chile - Spanish	es_cl
Colombia - Spanish	es_co
Costa Rica - Spanish	es_cr
Dominican Republic - Spanish	es_do
Ecuador - Spanish	es_ec
Guatemala - Spanish	es_gt
Guyana - English	en_gy
Honduras - Spanish	es_hn
Mexico - Spanish	es_mx
Nicaragua - Spanish	es_ni
Panama - Spanish	es_pa
Peru - Spanish	es_pe
Puerto Rico - Spanish	es_pr
Paraguay - Spanish	es_py
El Salvador - Spanish	es_sv
Uruguay - Spanish	es_uy
Venezuela - Spanish	es_ve

During an installation in one of the listed locales, the `Product Key` window (shown in Figure 4.2) will open, prompting you to provide a valid product key. Enter a product key, and press `Next` to continue with the installation.



*Figure 4.2 -The Advanced Server Product Key Window*

### **4.3 Performing a Graphical Installation**

A graphical installation wizard provides a quick and easy way to install Advanced Server 9.6 on a Linux or Windows system. As the `Setup` wizard's easy-to-follow dialogs lead you through the installation process, specify information about your system, your system usage, and the modules that will best complement your installation of Advanced Server. When you have completed the dialogs, the installer performs an installation based on the selections made during the setup process.


When the Advanced Server installation finishes, you will be offered the option to invoke EDB Postgres StackBuilder Plus. StackBuilder Plus provides an easy-to-use graphical interface that can update installed products, or download and add any omitted modules (and the resulting dependencies) after your Advanced Server setup and installation completes. See [Section 4.5](#) for more information about StackBuilder Plus.

### 4.3.1 Using the Graphical Installer with Windows

To perform an installation using the graphical wizard on a Windows system, you must have administrator privileges. To start the Setup wizard, assume administrator privileges, and double-click the `edb-as96-meta-9.6.x.x-windows-x64` executable file.

*To install Advanced Server on some versions of Windows you may be required to right click on the file and select `Run as Administrator` from the context menu to invoke the installer with `Administrator` privileges.*

The wizard opens a Language Selection popup; select an installation language from the drop-down listbox and click OK to continue. If you do not have Java installed on your system, the installer will ask you to confirm that you wish to continue the installation without installing Java based components; click Yes to continue to the Setup window (shown in Figure 4.3):



*Figure 4.3 -The Advanced Server installer Welcome window*

Click `Next` to continue.


The EnterpriseDB License Agreement (see Figure 4.4) opens.



*Figure 4.4 -The EnterpriseDB License Agreement*

Carefully review the license agreement before highlighting the appropriate radio button; click `Next` to continue.

The `User Authentication` window opens, as shown in Figure 4.5.




The screenshot shows a window titled "Setup" with a standard Windows title bar. The main content area is titled "User Authentication" and features the EDB Postgres logo in the top right corner. Below the logo, a message states: "This installation requires a registration with EnterpriseDB.com. Please enter your credentials below:". There are two input fields: "Email" and "Password". Below these fields, a message says: "If you do not have an account, please create one now by clicking the link below..." followed by a blue hyperlink: <https://www.enterprisedb.com/user-login-registration>. At the bottom left, the text "InstallBuilder" is visible. At the bottom right, there are three buttons: "< Back", "Next >", and "Cancel".

*Figure 4.5 -The User Authentication window.*

Before continuing, you must provide the email address and password associated with your EnterpriseDB user account. Registration is free; if you do not have an EnterpriseDB user account, click the link provided to open a web browser, and supply your user information.

Enter the email address of a registered account in the `Email` field, and the corresponding password in the `Password` field, and click `Next` to continue.

The `Installation Directory` window opens, as shown in Figure 4.6.




*Figure 4.6 -The Installation Directory window.*

By default, the Advanced Server installation directory is:

```
C:\Program Files\edb
```

You can accept the default installation location, and click `Next` to continue, or optionally click the `File Browser` icon to open the `Browse For Folder` dialog (shown in Figure 4.7) to choose an alternate installation directory.






*Figure 4.7 -The Browse For Folder dialog*

Use the tree control displayed on the `Browse For Folder` dialog to navigate to an alternate installation directory, or create a new installation directory by selecting the `Make New Folder` button, and entering a name for the new folder.

After selecting an alternate installation directory, click `OK` to continue. When you return to the `Installation Directory` window, click `Next` to open the `Select Components` window.



*Figure 4.8 -The Select Components window*

The `Select Components` window (shown in Figure 4.8) contains a list of optional components that you can install with the `Advanced Server Setup` wizard. Note that if you do not have Java installed on your system, those components that require Java are disabled and will not be installed. You can omit a module from the `Advanced Server` installation by deselecting the box next to the components name.

The `Setup` wizard can install the following components while installing `Advanced Server 9.6`:

### **EDB Postgres Advanced Server**

Select the `EDB Postgres Advanced Server` option to install `Advanced Server 9.6`.

### **EDB Postgres Connectors**

Select the `EDB Postgres Connectors` option to install the client connector API's for JDBC, .NET, OCI and ODBC. The client connectors facilitate application connectivity for `Advanced Server`.

### **EDB Postgres Migration Toolkit**

If you have Java (version 7 or 8) or OpenJDK (version 1.7 or 1.8) installed on your system, you can use the `EDB Postgres Migration Toolkit` option to install `Migration Toolkit`. `Migration Toolkit` is a command line migration utility that facilitates migration from MySQL, Oracle, Microsoft SQL Server and Sybase databases.

See the *EDB Postgres Migration Guide* for more information about `Migration Toolkit` available from the EnterpriseDB website at:

<http://www.enterprisedb.com/products-services-training/products/documentation/enterpriseedition>

### **EDB Postgres pgAdmin 4**

Select the `EDB Postgres pgAdmin 4` option to install the `pgAdmin 4` client. `pgAdmin 4` provides a powerful graphical interface for database management and monitoring.

### **EDB Postgres Advanced Server EDB\*Plus**

If you have Java installed on your system, you can select the `EDB Postgres Advanced Server EDB*Plus` option to install `EDB*Plus`. `EDB*Plus` is the `Advanced Server SQL` command line interface that offers compatibility with Oracle's `SQL Plus` commands.

## EDB Postgres Advanced Server Slony Replication

Check the box next to `EDB Postgres Advanced Server Slony Replication` to specify that Slony should be included in the installation process. Slony facilitates primary-standby replication suited for large databases with a limited number of standby systems.

## EDB Postgres PgBouncer

Select the `EDB Postgres pgBouncer` option to install PgBouncer. PgBouncer is a lightweight connection pooling utility for Advanced Server. Connection pooling can dramatically reduce processing time and resources for systems maintaining client connections to one or more databases.

StackBuilder Plus is included with the installation of Advanced Server and its core supporting components. The StackBuilder Plus utility is a graphical tool that can update installed products, or download and add any omitted modules (and the resulting dependencies) after your Advanced Server setup and installation completes. See Section [4.5](#) for more information about StackBuilder Plus.

After adjusting the list of modules or accepting the default and installing all modules, click `Next` to open the `Data Directory` window (shown in Figure 4.9).



*Figure 4.9 -The Data Directory window.*

By default, the Advanced Server data files are saved to:

```
C:\Program Files\edb\as9.6\data
```


You can accept the default location for the data files, or use the File Browser icon to open the Browse For Folder dialog.

The default location of the Advanced Server Write-Ahead Log (WAL) Directory is:

```
C:\Program Files\edb\as9.6\data\pg_xlog
```

Advanced Server uses write-ahead logs to promote transaction safety and speed transaction processing; when you make a change to a table, the change is stored in shared memory and a record of the change is written to the write-ahead log. When you perform a COMMIT, Advance Server writes contents of the write-ahead log to disk.

Accept the default file locations, or specify alternate locations with the File Browser icon; click Next to continue to the Configuration Mode window (shown in Figure 4.10).



*Figure 4.10 -The Configuration Mode window.*

Use the drop-down listbox on the `Configuration Mode` window to choose a server dialect. The server dialect specifies the compatibility features supported by Advanced Server.

By default, Advance Server installs in `Compatible with Oracle mode`; you can choose between `Compatible with Oracle` and `Compatible with PostgreSQL` installation modes.

## Compatible with Oracle

If you select `Compatible with Oracle` on the `Configuration Mode` dialog, the installation will include the following features:

- Data dictionary views compatible with Oracle databases.
- Oracle data type conversions.
- Date values displayed in a format compatible with Oracle syntax.
- Support for Oracle-styled concatenation rules (if you concatenate a string value with a `NULL` value, the returned value is the value of the string).
- Schemas (`dbo` and `sys`) compatible with Oracle databases added to the `SEARCH_PATH`.
- Support for the following Oracle built-in packages:

Package	Functionality Compatible with Oracle Databases
<code>dbms_alert</code>	Provides the ability to register for, send and receive alerts.
<code>dbms_crypto</code>	Provides a way to encrypt or decrypt RAW, BLOB or CLOB data.
<code>dbms_job</code>	Implements job-scheduling functionality.
<code>dbms_lob</code>	Provides the ability to manage large objects.
<code>dbms_lock</code>	Provides support for the <code>DBMS_LOCK.SLEEP</code> procedure.
<code>dbms_mview</code>	Provides a way to manage and refresh materialized views.
<code>dbms_output</code>	Provides the ability to display a message on the client.
<code>dbms_pipe</code>	Provides the ability to send a message from one session and read it in another session.
<code>dbms_profiler</code>	Collects and stores performance data about PL/pgSQL and SPL statements.
<code>dbms_random</code>	Provides a way to generate random numbers.
<code>dbms_ols</code>	Implements row level security.
<code>dbms_scheduler</code>	Provides a way to create and manage Oracle-style jobs.
<code>dbms_session</code>	A partial implementation that provides support for <code>DBMS_SESSION.SET_ROLE</code> .
<code>dbms_sql</code>	Implements use of Dynamic SQL
<code>dbms_utility</code>	Provides a collection of misc functions and procedures.
<code>utl_encode</code>	Provides a way to encode or decode data.
<code>utl_file</code>	Provides a way for a function, procedure or anonymous block to interact with files stored in the server's file system.
<code>utl_http</code>	Provides a way to use HTTP or HTTPS to retrieve information found at a URL.
<code>utl_mail</code>	Provides a simplified interface for sending email and attachments.

<b>Package</b>	<b>Functionality Compatible with Oracle Databases</b>
utl_raw	Provides a way to manipulate or retrieve the length of raw data types.
utl_smtp	Implements smtp email functions.
utl_url	Provides a way to escape illegal and reserved characters in a URL.

This is not a comprehensive list of the compatibility features for Oracle included when Advanced Server is installed in `Compatible with Oracle` mode; more information about Advanced Server is found in the *Database Compatibility for Oracle Developer's Guide* available from the EnterpriseDB website at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

If you choose to install in `Compatible with Oracle` mode, the Advanced Server superuser name is `enterprisedb`.


### **Compatible with PostgreSQL**

When installed in `Compatible with PostgreSQL` mode, Advanced Server exhibits complete compatibility with PostgreSQL version 9.6. If you choose to install in `Compatible with PostgreSQL` mode, the Advanced Server superuser name is `postgres`.

For detailed information about PostgreSQL functionality, visit the official PostgreSQL website at:

<http://www.postgresql.org>

After specifying a configuration mode, click `Next` to continue to the `Password` window (shown in Figure 4.11).




*Figure 4.11 -The Password window.*

Advanced Server uses the password specified on the `Password` window for the database superuser and the `pgAgent` service. The specified password must conform to any security policies existing on the Advanced Server host.

After you enter a password in the `Password` field, confirm the password in the `Retype Password` field, and click `Next` to continue.

The `Additional Configuration` window opens (shown in Figure 4.12).



*Figure 4.12 -The Additional Configuration window.*


Use the fields on the Additional Configuration window to specify installation details:

- Use the `Port` field to specify the port number that Advanced Server should listen to for connection requests from client applications. The default is 5444.
- If the `Locale` field is set to `[Default locale]`, Advanced Server uses the system locale as the working locale. Use the drop-down listbox next to `Locale` to specify an alternate locale for Advanced Server.
- By default, the Setup wizard installs corresponding sample data for the server dialect specified by the compatibility mode (Oracle or PostgreSQL). Clear the checkbox next to `Install sample tables and procedures` if you do not wish to have sample data installed.

After verifying the information on the Additional Configuration window, click `Next` to open the `Dynatune Dynamic Tuning: Server Utilization` window (shown in Figure 4.13).

The graphical Setup wizard facilitates performance tuning via the Dynatune Dynamic Tuning feature. Dynatune functionality allows Advanced Server to make optimal usage of the system resources available on the host machine on which it is installed.






*Figure 4.13 -The Dynatune Dynamic Tuning: Server Utilization window.*

The `edb_dynatune` configuration parameter determines how Advanced Server allocates system resources. Use the radio buttons on the Server Utilization window to set the initial value of the `edb_dynatune` configuration parameter:

- Select `Development` to set the value of `edb_dynatune` to 33. A low value dedicates the least amount of the host machine's resources to the database server. This is a good choice for a development machine.
- Select `General Purpose` to set the value of `edb_dynatune` to 66. A mid-range value dedicates a moderate amount of system resources to the database server. This would be a good setting for an application server with a fixed number of applications running on the same host as Advanced Server.
- Select `Dedicated` to set the value of `edb_dynatune` to 100. A high value dedicates most of the system resources to the database server. This is a good choice for a dedicated server host.

After the installation is complete, you can adjust the value of `edb_dynatune` by editing the `postgresql.conf` file, located in the `data` directory of your Advanced Server installation. After editing the `postgresql.conf` file, you must restart the server for your changes to take effect.

Select the appropriate setting for your system, and click `Next` to continue to the `Dynatune Dynamic Tuning: Workload Profile` window (shown in Figure 4.14).



*Figure 4.14 -The Dynatune Dynamic Tuning: Workload Profile window.*

Use the radio buttons on the `Workload Profile` window to specify the initial value of the `edb_dynatune_profile` configuration parameter. The `edb_dynatune_profile` parameter controls performance-tuning aspects based on the type of work that the server performs.

- Select `Transaction Processing (OLTP systems)` to specify an `edb_dynatune_profile` value of `oltp`. Recommended when Advanced Server is supporting heavy online transaction processing.
- Select `General Purpose (OLTP and reporting workloads)` to specify an `edb_dynatune_profile` value of `mixed`. Recommended for servers that provide a mix of transaction processing and data reporting.
- Select `Reporting (Complex queries or OLAP workloads)` to specify an `edb_dynatune_profile` value of `reporting`. Recommended for database servers used for heavy data reporting.


After the installation is complete, you can adjust the value of `edb_dynatune_profile` by editing the `postgresql.conf` file, located in the `data` directory of your Advanced

Server installation. After editing the `postgresql.conf` file, you must restart the server for your changes to take effect.

For more information about `edb_dynatune` and other performance-related topics, see the *EDB Postgres Advanced Server Guide* available from the EnterpriseDB website at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

Click **Next** to continue. The Advanced Configuration window (shown in Figure 4.15) opens.



*Figure 4.15 -The Advanced Configuration window.*

## PgBouncer

PgBouncer is a lightweight connection pooling utility for Advanced Server. Connection pooling can dramatically reduce processing time and resources for systems maintaining client connections to one or more databases. By default, Advanced Server expects PgBouncer to listen on port 6432.

Please note that the PgBouncer program stores a list of users and passwords in clear-text form in the following file:

```
C:\Program Files\edb\pgbouncer1.7\etc\userlist.txt
```

By default, the file is located in a directory that is accessible only to the cluster owner (by default, `enterprisedb`), but administrators should take note of the file and maintain permissions in a manner that secures the file from untrusted users

For more information about PgBouncer, visit the project site at:

<https://wiki.postgresql.org/wiki/PgBouncer>

### **pgAgent**


pgAgent is a job scheduling agent for Postgres, capable of running multi-step batch/shell and SQL tasks on complex schedules. pgAgent also provides background support for the `DBMS_JOB` built-in package that is compatible with Oracle databases.

### **Update Notification Service**

When enabled, the Update Notification Service notifies you of any new updates and security patches available for your installation of Advanced Server.

By default, Advanced Server is configured to start the the PgBouncer, pgAgent and Update Notification Service services when the system boots; clear applicable `Service Configuration` checkboxes, or accept the defaults, and click `Next` to continue.


The `Pre Installation Summary` opens as shown in Figure 4.16.



*Figure 4.16 -The Pre Installation Summary.*


The Pre Installation Summary provides an overview of the options specified during the Setup process. Review the options before clicking Next; use the Back button to navigate back through the dialogs and update any options.

The `Ready to Install` window (see Figure 4.17) confirms that the installer has the information it needs about your configuration preferences to install Advanced Server. Click `Next` to continue.




*Figure 4.17 -The Ready to Install window.*

As each supporting module is unpacked and installed, the module's installation is confirmed with a progress bar (see Figure 4.18).



*Figure 4.18 -Popup dialogs confirm the installation of supporting modules.*

Before the Setup wizard completes the Advanced Server installation, it offers to Launch StackBuilder Plus at exit? (see Figure 4.19).



*Figure 4.19 -The Setup wizard offers to Launch StackBuilder Plus at exit.*

You can clear the StackBuilder Plus checkbox and click Finish to complete the Advanced Server installation, or accept the default and proceed to StackBuilder Plus.


EDB Postgres StackBuilder Plus is included with the installation of Advanced Server and its core supporting components. StackBuilder Plus is a graphical tool that can update installed products, or download and add any omitted modules (and the resulting dependencies) after your Advanced Server setup and installation completes. See [Section 4.5](#) for more information about StackBuilder Plus.

### 4.3.2 Using the Graphical Installer on a Linux System

To use the graphical installation wizard on a Linux system, you must have superuser privileges. To invoke the Setup wizard, open a Terminal window, navigate to the directory that contains the unpacked Advanced Server binary file, and enter the command:

```
./edb-as96-meta-9.6.x.x-linux-x64.run
```

The wizard opens a Language Selection popup; select an installation language from the drop-down listbox and click OK to continue. If you do not have Java installed on your system, the installer will ask you to confirm that you wish to continue the installation without installing Java based components; click Yes to continue to the Setup window (shown in Figure 4.20).




*Figure 4.20 -The Advanced Server installer Setup welcome.*

Click Next to continue.




The License Agreement window (shown in Figure 4.21) opens.



*Figure 4.21 -The EnterpriseDB License Agreement.*

Review the EnterpriseDB License Agreement carefully before selecting the radio button next to I accept the agreement. Click Next to continue to the User Authentication window.


The `User Authentication` window opens, as shown in Figure 4.22.



*Figure 4.22 -The User Authentication window.*

Before continuing, you must provide the email address and password associated with your EnterpriseDB user account. Registration is free; if you do not have an EnterpriseDB user account, click the link provided to open a web browser, and enter your user information.

Enter the email address of a registered account in the `Email` field, and the corresponding password in the `Password` field, and click `Next` to continue to the `Installation Directory` window (see Figure 4.23).




*Figure 4.23 -The Installation Directory window.*

By default, the Advanced Server installation directory is:

`/opt/edb`


You can accept the default installation location, and click `Next` to continue, or click the `File Browser` icon to open a `Select File` dialog (shown in Figure 4.24) to choose an alternate installation directory.



*Figure 4.24 -The Select File dialog.*

Use the `Select File` dialog to navigate to an alternate installation directory, or create a new installation directory by selecting the `Add Folder` icon, and entering a name for the new folder.

After selecting an alternate installation directory, click `Open` to continue. When you return to the `Installation Directory` window, click `Next` to open the `Select Components` window.



*Figure 4.25 -The Select Components window.*

The `Select Components` window (shown in Figure 4.25) contains a list of the utilities that you can install with the Advanced Server `Setup` wizard. If your system does not include a Java installation, those components dependent on Java will be disabled and will not install. You can skip the installation of a module by clearing the x mark next to the component name.

The `Setup` wizard can install the following components while installing Advanced Server 9.6:

### **EDB Postgres Advanced Server 9.6**

Select the `EDB Postgres Advanced Server` option to install Advanced Server 9.6.

### **EDB Postgres Connectors**

Select the `EDB Postgres Connectors` option to install the client connector API's for JDBC, OCI and ODBC. The client connectors facilitate application connectivity for Advanced Server.

## EDB Postgres Advanced Server Infinite Cache

Select the `EDB Postgres Advanced Server Infinite Cache` option to install the `edb-icache` daemon. With Infinite Cache, Advanced Server will be able to utilize memory from other computers connected to your network to avoid reading frequently accessed data from disk.

The `Setup` wizard can optionally install the Infinite Cache daemon on a remote `icache` server without including a complete installation of Advanced Server. To install only the `edb-icache` daemon, deselect the other components shown on the `Select Components` window before clicking `Next`.

For more information about using Infinite Cache and the `edb-icache` daemon, see the *EDB Postgres Advanced Server Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

## EDB Postgres Migration Toolkit

If you have Java (version 7 or 8) or OpenJDK (version 1.7 or 1.8) installed on your system, you can use the `EDB Postgres Migration Toolkit` option to install Migration Toolkit. Migration Toolkit is a command line migration utility that facilitates migration from MySQL, Oracle, Microsoft SQL Server and Sybase databases. See the *EDB Postgres Migration Guide* for more information about Migration Toolkit available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

## EDB Postgres pgAdmin 4

Select the `EDB Postgres pgAdmin 4` option to install the pgAdmin 4 client. pgAdmin 4 provides a powerful graphical interface for database management and monitoring.

## EDB Postgres pgPool-II

Use the `EDB Postgres pgPool-II` option to include pgPool-II in the Advanced Server installation. pgPool-II provides load balancing, connection pooling, high availability, and connection limits for Advanced Server databases.

## EDB Postgres pgPool-II Extensions

If you are installing pgPool-II, check the box next to `EDB Postgres pgPool-II Extensions` to include the server extensions required by the server to implement pgPool-II functionality.

### **EDB Postgres Advanced Server EDB\*Plus**

Select the `EDB Postgres Advanced Server EDB*Plus` option to install EDB\*Plus. EDB\*Plus is the Advanced Server command line interface that offers compatibility with Oracle's SQL Plus commands.

Please note that the EDB\*Plus installation option will only be enabled if your system contains Java.

### **EDB Postgres Advanced Server Slony Replication**


Check the box next to `EDB Postgres Advanced Server Slony Replication` to specify that Slony should be included in the Advanced Server installation. Slony facilitates primary-standby replication suited for large databases with a limited number of standby systems.

### **EDB Postgres PgBouncer**

Check the box next to `EDB Postgres pgBouncer` to specify that PgBouncer should be included in the Advanced Server installation. PgBouncer is a lightweight connection pooling utility for Advanced Server. Connection pooling can dramatically reduce processing time and resources for systems maintaining client connections to one or more databases.

StackBuilder Plus is included with the installation of Advanced Server and its core supporting components. The StackBuilder Plus utility is a graphical tool that can update installed products, or download and add any omitted modules (and the resulting dependencies) after your Advanced Server setup and installation completes. See [Section 4.5](#) for more information about StackBuilder Plus.

After editing the list of supporting components, click `Next` to open the `Additional Directories` window (shown in Figure 4.26).



*Figure 4.26 -The Additional Directories window.*

Use the fields in the `Additional Directories` window to specify locations for the `Advanced Server Data Directory` and `Write-Ahead Log (WAL) Directory`.


The default `Data Directory` is `/opt/edb/as9.6/data`. You can use the file selector icon to specify an alternate location.

The default location of the `Advanced Server Write-Ahead Log (WAL) Directory` is `opt/edb/as9.6/data/pg_xlog`. Accept the default location, or specify an alternate location with the file selector icon.

`Advanced Server` uses write-ahead logs to promote transaction safety and speed transaction processing; when you make a change to a table, the change is stored in shared memory and a record of the change is written to the write-ahead log. When you perform a `COMMIT`, `Advance Server` writes contents of the write-ahead log to disk.

Click `Next` to continue to the `Configuration Mode` window (shown in Figure 4.27).





*Figure 4.27 -The Configuration Mode window.*

Use the drop-down listbox on the Configuration Mode window to choose a server dialect. The server dialect specifies the compatibility features supported by Advanced Server.

By default, Advance Server installs with database compatibility with Oracle; you can choose between Compatible with Oracle and Compatible with PostgreSQL installation modes.

### **Compatible with Oracle Mode**

If you select Compatible with Oracle in the Configuration Mode dialog, the installation will include the following features:

- Dictionary views compatible with Oracle databases.
- Oracle data type conversions.
- Date values displayed in a format compatible with Oracle syntax.

- Oracle-styled concatenation rules (if you concatenate a string value with a `NULL` value, the returned value is the value of the string).
- Schemas (`dbo` and `sys`) compatible with Oracle databases added to the `SEARCH_PATH`.
- Support for the following Oracle built-in packages:

Package	Functionality Compatible with Oracle Databases
<code>dbms_alert</code>	Provides the ability to register for, send and receive alerts.
<code>dbms_crypto</code>	Provides a way to encrypt or decrypt RAW, BLOB or CLOB data.
<code>dbms_job</code>	Implements job-scheduling functionality.
<code>dbms_lob</code>	Provides the ability to manage large objects.
<code>dbms_lock</code>	Provides support for the <code>DBMS_LOCK.SLEEP</code> procedure.
<code>dbms_mview</code>	Provides a way to manage and refresh materialized views.
<code>dbms_output</code>	Provides the ability to display a message on the client.
<code>dbms_pipe</code>	Provides the ability to send a message from one session and read it in another session.
<code>dbms_profiler</code>	Collects and stores performance data about PL/pgSQL and SPL statements.
<code>dbms_random</code>	Provides a way to generate random numbers.
<code>dbms_ols</code>	Implements row level security.
<code>dbms_scheduler</code>	Provides a way to create and manage Oracle-style jobs.
<code>dbms_session</code>	A partial implementation that provides support for <code>DBMS_SESSION.SET ROLE</code> .
<code>dbms_sql</code>	Implements use of Dynamic SQL
<code>dbms_utility</code>	Provides a collection of misc functions and procedures.
<code>utl_encode</code>	Provides a way to encode or decode data.
<code>utl_file</code>	Provides a way for a function, procedure or anonymous block to interact with files stored in the server's file system.
<code>utl_http</code>	Provides a way to use HTTP or HTTPS to retrieve information found at a URL.
<code>utl_mail</code>	Provides a simplified interface for sending email and attachments.
<code>utl_raw</code>	Provides a way to manipulate or retrieve the length of raw data types.
<code>utl_smtp</code>	Implements smtp email functions.
<code>utl_url</code>	Provides a way to escape illegal and reserved characters in a URL.

This is not a comprehensive list of the compatibility features for Oracle included when Advanced Server is installed in `Compatible with Oracle` mode. For more information, refer to the *Database Compatibility for Oracle Developer's Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

If you choose to install in `Compatible with Oracle` mode, the Advanced Server superuser name is `enterprisedb`.

## Compatible with PostgreSQL Mode


When installed in `Compatible with PostgreSQL` mode, Advanced Server exhibits complete compatibility with Postgres version 9.6.

For more information about PostgreSQL functionality, visit the official PostgreSQL website at:

<http://www.postgresql.org>

If you choose to install in `Compatible with PostgreSQL` mode, the Advanced Server superuser name is `postgres`.


After specifying a configuration mode, click `Next` to continue to the `Password` window (shown in Figure 4.28).



*Figure 4.28 -The Password window.*

Advanced Server uses the password specified in the `Password` window for the database superuser and `pgAgent` service. The specified password must conform to any security policies existing on the Advanced Server host.

After you enter a password in the `Password` field, confirm the password in the `Retype Password` field, and click `Next` to continue.




*Figure 4.29 -The Additional Configuration window.*

Use the fields on the `Additional Configuration` window (shown in Figure 4.29) to specify installation details:

- Use the `Port` field to specify the port number that Advanced Server should listen to for connection requests from client applications. The default is `5444`.
- If the `Locale` field is set to `[Default Locale]`, Advanced Server uses the system locale as the working locale. Use the drop-down listbox next to `Locale` to specify an alternate locale for Advanced Server.
- By default, the `Setup` wizard installs corresponding sample data for the server dialect specified by the compatibility mode (`Oracle` or `PostgreSQL`). Clear the checkbox next to `Install sample tables and procedures` if you do not wish to have sample data installed.

After verifying the selections on the `Additional Configuration` window, click `Next` to open the `Dynatune Dynamic Tuning: Server Utilization` window (shown in Figure 4.30).

The `Setup` wizard facilitates performance tuning via the `Dynatune Dynamic Tuning` feature. `Dynatune` functionality allows `Advanced Server` to make optimal usage of the system resources available on the host machine.



*Figure 4.30 -The Server Utilization window.*

The `edb_dynatune` configuration parameter determines how `Advanced Server` allocates system resources. The radio buttons on the `Server Utilization` window set the initial value of the `edb_dynatune` configuration parameter.


- Select `Development` to set the value of `edb_dynatune` to 33. A low value dedicates the least amount of the host machine's resources to the database server. This is a good choice for a development machine.
- Select `General Purpose` to set the value of `edb_dynatune` to 66. A mid-range value dedicates a moderate amount of system resources to the database

server. This would be a good setting for an application server with a fixed number of applications running on the same host as Advanced Server.

- Select `Dedicated` to set the value of `edb_dynatune` to 100. A high value dedicates most of the system resources to the database server. This is a good choice for a dedicated server host.

After the installation is complete, you can adjust the value of `edb_dynatune` by editing the `postgresql.conf` file, located in the `data` directory of your Advanced Server Installation. After editing the `postgresql.conf` file, you must restart the server for the changes to take effect.

Select the appropriate setting for your system, and click `Next` to continue to the `Dynatune Dynamic Tuning: Workload Profile` window (shown in Figure 4.31).



*Figure 4.31 -The Workload Profile window.*

Use the radio buttons on the `Workload Profile` window to specify the initial value of the `edb_dynatune_profile` configuration parameter. The `edb_dynatune_profile` parameter controls performance-tuning aspects based on the type of work that the server performs.


- **Select Transaction Processing (OLTP systems)** to specify an `edb_dynatune_profile` value of `oltp`. Recommended when Advanced Server is supporting heavy online transaction processing workloads.
- **Select General Purpose (OLTP and reporting workloads)** to specify an `edb_dynatune_profile` value of `mixed`. Recommended for servers that provide a mix of transaction processing and data reporting.
- **Select Reporting (Complex queries or OLAP workloads)** to specify an `edb_dynatune_profile` value of `reporting`. Recommended for database servers used for heavy data reporting.

After the installation is complete, you can adjust the value of `edb_dynatune_profile` by editing the `postgresql.conf` file, located in the `data` directory of your Advanced Server installation. After editing the `postgresql.conf` file, you must restart the server for the changes to take effect.

For more information about `edb_dynatune` and other performance-related topics, see the *EDB Postgres Advanced Server Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

After selecting the radio button that best describes the use of the system, click `Next` to continue. The `Advanced Configuration` window (shown in Figure 4.32) opens.



*Figure 4.32 -The Advanced Configuration window.*

## PgBouncer

PgBouncer is a lightweight connection pooling utility for Advanced Server. Connection pooling can dramatically reduce processing time and resources for systems maintaining client connections to one or more databases. By default, Advanced Server expects PgBouncer to listen on port 6432.

Please note that the PgBouncer program stores a list of users and passwords in clear-text form in the following file:

```
/opt/edb/pgbouncer1.7/etc/userlist.txt
```

The file is located in a directory that is accessible only to the cluster owner (by default, `enterprisedb`), but administrators should take note of the file and maintain permissions in a manner that secures the file from untrusted users.

For more information about PgBouncer, visit:

<http://wiki.postgresql.org/wiki/PgBouncer>



## pgAgent


pgAgent is a job scheduling agent for Postgres, capable of running multi-step batch/shell and SQL tasks on complex schedules. pgAgent also provides background support for the DBMS\_JOB built-in package compatible with Oracle databases.

## Update Notification Service

When enabled, the Update Notification Service notifies you of any new updates and security patches available for your installation of Advanced Server.

By default, Advanced Server is configured to start the PgBouncer, pgAgent and Update Notification Service services when the system boots; clear applicable `Service Configuration` checkboxes, or accept the defaults, and click `Next` to continue.


The `Pre Installation Summary` window opens (shown in Figure 4.33).



*Figure 4.33 -The Pre Installation Summary.*


The `Pre Installation Summary` provides an overview of the options specified during the `Setup` process. Review the options before clicking `Next`; use the `Back` button to navigate back through the dialogs to update any options.

The `Ready to Install` window (shown in Figure 4.34) confirms that the installer has the information it needs about your configuration preferences to install Advanced Server.



*Figure 4.34 -The Ready to Install window.*

Click `Next` to continue. The `Setup` wizard confirms the installation progress of Advanced Server via a series of progress bars (shown in Figure 4.35).



*Figure 4.35 -Popup dialogs confirm the installation progress.*

Before the Setup wizard completes the Advanced Server installation, it offers to Launch Stack Builder Plus at exit? (see Figure 4.36).



*Figure 4.36 -The Setup wizard offers to Launch StackBuilder Plus at exit.*

You can clear the StackBuilder Plus checkbox and click Finish to complete the Advanced Server installation, or you can accept the default and proceed to StackBuilder Plus.

StackBuilder Plus provides a graphical interface that updates, downloads and installs applications and drivers that work with Advanced Server. For more information about StackBuilder Plus, see Section [4.5](#), *Using StackBuilder Plus*.

## 4.4 Invoking the Installer from the Command Line

The command line options of the Advanced Server installer offer functionality in situations where a graphical installation may not work because of limited resources or privileges. You can:

- Include the `--mode unattended` option when invoking the installer to perform an installation without user input.
- Include the `--mode text` option when invoking the installer to perform an installation from the command line.
- Invoke the installer with the `--extract-only` option to perform a minimal installation when you don't hold the privileges required to perform a complete installation.

Not all command line options are suitable for all platforms. For a complete reference guide to the command line options, see Section [4.4.4, Reference - Command Line Options](#).

Please note: If you are invoking the installer from the command line to perform a system upgrade, the installer will ignore command line options, and preserve the configuration of the previous installation.

### 4.4.1 Performing a Text Mode Installation

To specify that the installer should run in text mode, include the `--mode text` command line option when invoking the installer. Text-mode installations are useful if you need to install on a remote server using ssh tunneling (and have access to a minimal amount of bandwidth), or if you do not have access to a graphical interface.

In text mode, the installer uses a series of command line questions to establish the configuration parameters. Text-mode installations are valid only on Linux systems.

You must assume superuser privileges before performing a text-mode installation. To perform a text-mode installation on a Linux system, navigate to the directory that contains the installation binary file and enter:

```
# ./edb-as96-meta-9.6.x.x-linux-x64.run --mode text
```

At any point during the installation process, you can press `Ctrl-C` to abort the installation.

The installer starts, prompting you to select an installation language:

```
Language Selection

Please select the installation language
[1] English - English
[2] Japanese - 日本語
[3] Simplified Chinese - 简体中文
[4] Traditional Chinese - 繁体中文
[5] Korean - 한국어
Please choose an option [1] :
```

The installation language is the language used by the installer during the installation process. The default value for `English` is displayed in square braces immediately to the left of the prompt (`[1]`); press `Enter` to accept the default value and continue, or change the value to specify an alternate installation language.

If the installer detects that you do not have Java installed on your system, it will alert you that it will not install Java-based components. Select `Y` or `Enter` to continue, or exit the installation and install Java before re-opening the installer.

The text mode installer welcomes you to the `Setup Wizard`, and introduces the `License Agreement`. Use the `Enter` key to page through the license agreement:

## EDB Postgres Advanced Server Installation Guide

Welcome to the EDB Postgres Advanced Server Setup Wizard.  
This is a public beta test build intended for testing only.  
NOT FOR PRODUCTION USE.

If you have any issues or problems to report, please visit:  
<http://forums.enterprisedb.com>

-----  
Please read the following License Agreement. You must  
accept the terms of this agreement before continuing with  
the installation.

Press [Enter] to continue:

Press Enter to continue reviewing the license agreement. After displaying the license, the installer prompts you to accept the license:

Do you accept this license? [y/n]:

After reading the license agreement, enter `y` to accept the agreement and proceed with the installation. Enter `n` if you do not accept the license agreement; this will abort the installation.

Press Enter to proceed.

Next, Advanced Server will prompt you for the User Authentication information associated with your EnterpriseDB user account. There is no charge to register for an EnterpriseDB user account; if you do not have a user account, visit <http://www.enterprisedb.com/user-login-registration> to register.

This installation requires a registration with EnterpriseDB.com. Please enter your credentials below. If you do not have an account, Please create one now on <https://www.enterprisedb.com/user-login-registration>

When prompted, enter the email address of a registered account, and then the corresponding password:

Email []:

Password :

By default, Advanced Server is installed in `/opt/edb`:

Please specify the directory where EDB Postgres Advanced Server will be installed.

Installation Directory [/opt/edb]:

Enter an alternate location, or press Enter to accept the default and continue to the component selection portion of the installation process

Next, the installer prompts you individually for each component that is to be installed with Advanced Server:

```
Select the components you want to install.
```

Enter `Y` or press `Enter` to accept the default value of `yes` after each component that you wish to include with the installation. Enter `n` to omit a component from the installation.

```
EDB Postgres Advanced Server [Y/n] :
EDB Postgres Connectors [Y/n] :
EDB Postgres Advanced Server Infinite Cache [Y/n] :
EDB Postgres Migration Toolkit [Y/n] :
EDB Postgres pgAdmin 4 [Y/n] :
EDB Postgres pgPool-II [Y/n] :
EDB Postgres pgPool-II Extensions [Y/n] :
EDB Postgres Advanced Server EDB*Plus [Y/n] :
EDB Postgres Advanced Server Slony Replication [Y/n] :
EDB Postgres pgBouncer [Y/n] :
```

The Advanced Server components are:

### **EDB Postgres Advanced Server**

Press `Y` or `enter` after the `EDB Postgres Advanced Server` option to install Advanced Server 9.6.

### **EDB Postgres Connectors**

Press `Y` or `enter` after the `EDB Postgres Connectors` option to install the client connector API's for JDBC, .NET, OCI and ODBC. The client connectors facilitate application connectivity for Advanced Server.

### **EDB Postgres Advanced Server Infinite Cache**

Press `Y` or `enter` after the `EDB Postgres Advanced Server Infinite Cache` option to install the Infinite Cache daemon.

The Setup wizard can optionally install the `edb-icache` daemon on a remote icache server without including a complete installation of Advanced Server. To install only the `edb-icache` daemon, enter `n` after all other options before you confirm your selections.

For more information about using Infinite Cache and the `edb-icache` daemon, see the *EDB Postgres Advanced Server Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

### **EDB Postgres Migration Toolkit**

Press `Y` or `enter` after the `EDB Postgres Migration Toolkit` option to install Migration Toolkit. Migration Toolkit is a command line migration utility that facilitates migration from MySQL, Oracle, Microsoft SQL Server and Sybase databases. See the *EDB Postgres Migration Guide* for more information about Migration Toolkit available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

### **EDB Postgres pgAdmin 4**

Press `Y` or `enter` after the `EDB Postgres pgAdmin 4` option to install the pgAdmin 4 client. pgAdmin 4 provides a powerful graphical interface for database management and monitoring.

### **EDB Postgres pgPool-II**

Press `Y` or `enter` after the `EDB Postgres pgPool-II` option to install pgPool-II. pgPool-II provides load balancing, connection pooling, high availability, and connection limits for Advanced Server databases.

### **EDB Postgres pgPool-II Extensions**

If you are installing pgPool-II, include the `EDB Postgres pgPool-II Extensions` to provide the extensions required by the server to implement pgPool-II functionality.

### **EDB Postgres Advanced Server EDB\*Plus**

Press `Y` or `enter` after the `EDB Postgres Advanced Server EDB*Plus` option to install EDB\*Plus. EDB\*Plus is the Advanced Server command line interface that offers compatibility with Oracle's SQL Plus commands.

### **EDB Postgres Advanced Server Slony Replication**

Press `Y` or `enter` after the `EDB Postgres Advanced Server Slony Replication` option to specify that Slony should be included in the Advanced Server installation. Slony facilitates primary-standby replication suited for large databases with a limited number of standby systems.

### **EDB Postgres PgBouncer**

Press `Y` or `enter` after the `EDB Postgres PgBouncer` option to install PgBouncer. PgBouncer is a lightweight connection pooling utility for Advanced Server. Connection



pooling can dramatically reduce processing time and resources for systems maintaining client connections to one or more databases.

After selecting components for installation, confirm that the list is correct by entering `Y`; enter `n` to iterate through the list of components a second time.

```
Is the selection above correct? [Y/n]:
```

Next, the installer prompts you to specify the location of the `Additional Directories` required by Advanced Server. The default data directory is `/opt/edb/as9.6/data`. You can specify an alternate location, or press `Enter` to accept the default and continue.

```
Please select a directory under which to store your data.
Data Directory [/opt/edb/as9.6/data]:
```

The default location of the Advanced Server `Write-Ahead Log (WAL) Directory` is `/opt/edb/as9.6/data/pg_xlog`. Press `Enter` to accept the default location and continue, or specify an alternate location.

```
Please select a directory under which to store your Write-
Ahead Logs.
Write-Ahead Log (WAL) Directory
[/opt/edb/as9.6/data/pg_xlog]:
```

Advanced Server uses write-ahead logs to help ensure transaction safety and speed transaction processing; when you make a change to a table, the change is stored in shared memory and a record of the change is written to the write-ahead log. When you `COMMIT` a transaction, Advance Server writes contents of the write-ahead log to disk.

Next, the installer prompts you to select a `Configuration Mode`:

```
EDB Postgres Advanced Server always installs with database
compatibility features for Oracle(R) and maintains full
PostgreSQL compliance. Select your style preference for
installation defaults and samples.
```

```
The Oracle configuration will cause the use of certain
objects (e.g. DATE data types, string operations, etc.) to
produce results compatible with Oracle, create the same
Oracle sample tables, and have the database match Oracle
examples used in the documentation.
```

```
Configuration Mode
```

```
[1] Compatible with Oracle
[2] Compatible with PostgreSQL
Please choose an option [1] :
```

The configuration mode specifies the server dialect with which Advanced Server will be compatible; you can choose between `Compatible with Oracle` and `Compatible with PostgreSQL` installation modes.

### Compatible with Oracle Mode

Installing Advanced Server in `Compatible with Oracle` mode provides the following functionality:

- Data dictionary views and data type conversions compatible with Oracle databases.
- Date values displayed in a format compatible with Oracle syntax.
- Oracle-styled concatenation rules (if you concatenate a string value with a `NULL` value, the returned value is the value of the string).
- Schemas (`dbo` and `sys`) compatible with Oracle databases added to the `SEARCH_PATH`.
- Support for the following Oracle built-in packages:

Package	Functionality Compatible with Oracle Databases
<code>dbms_alert</code>	Provides the ability to register for, send and receive alerts.
<code>dbms_crypto</code>	Provides a way to encrypt or decrypt RAW, BLOB or CLOB data.
<code>dbms_job</code>	Implements job-scheduling functionality.
<code>dbms_lob</code>	Provides the ability to manage large objects.
<code>dbms_lock</code>	Provides support for the <code>DBMS_LOCK.SLEEP</code> procedure.
<code>dbms_mview</code>	Provides a way to manage and refresh materialized views.
<code>dbms_output</code>	Provides the ability to display a message on the client.
<code>dbms_pipe</code>	Provides the ability to send a message from one session and read it in another session.
<code>dbms_profiler</code>	Collects and stores performance data about PL/pgSQL and SPL statements.
<code>dbms_random</code>	Provides a way to generate random numbers.
<code>dbms_qls</code>	Implements row level security.
<code>dbms_scheduler</code>	Provides a way to create and manage Oracle-style jobs.
<code>dbms_session</code>	A partial implementation that provides support for <code>DBMS_SESSION.SET ROLE</code> .
<code>dbms_sql</code>	Implements use of Dynamic SQL
<code>dbms_utility</code>	Provides a collection of misc functions and procedures.
<code>utl_encode</code>	Provides a way to encode or decode data.
<code>utl_file</code>	Provides a way for a function, procedure or anonymous block to interact with files stored in the server's file system.
<code>utl_http</code>	Provides a way to use HTTP or HTTPS to retrieve information found at a URL.
<code>utl_mail</code>	Provides a simplified interface for sending email and attachments.
<code>utl_raw</code>	Provides a way to manipulate or retrieve the length of raw data types.
<code>utl_smtp</code>	Implements smtp email functions.
<code>utl_url</code>	Provides a way to escape illegal and reserved characters in a URL.

This is not a comprehensive list of the compatibility features for Oracle included when Advanced Server is installed in `Compatible with Oracle` mode; more information about Advanced Server is available in the *Database Compatibility for Oracle Developer's Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation/enterpriseedition>

If you choose to install in `Compatible with Oracle` mode, the Advanced Server superuser name is `enterprisedb`.

### **Compatible with PostgreSQL Mode**

When installed in `Compatible with PostgreSQL` mode, Advanced Server exhibits complete compatibility with Postgres version 9.6. For more information about PostgreSQL functionality, visit the official PostgreSQL website at:

<http://www.postgresql.org>

If you choose to install in `Compatible with PostgreSQL` mode, the Advanced Server superuser name is `postgres`.

Press `Enter` to accept the default configuration mode (`Compatible with Oracle`) and continue; enter `2` and press `Enter` to install in `Compatible with PostgreSQL` mode.

Next, the installer prompts you for a database superuser password:

```
Please provide a password for the database superuser
(enterprisedb). A locked Unix user account (enterprisedb)
will be created if not present.
```

```
Password :
```

```
Retype Password :
```

Advanced Server uses the password specified for the database superuser and `pgAgent` service. The specified password must conform to any security policies existing on the Advanced Server host.

After entering a password in the `Password` field, confirm the password and press `Enter` to continue.

The installer prompts you for `Additional Configuration` information:

```
Additional Configuration
```

When prompted, enter the `Port` that the Advanced Server service will monitor for connections. By default, Advanced Server chooses the first available port after port number 5444:

```
Please select the port number the server should listen on.
```

```
Port [5444]:
```

Specify a `Locale` by entering a locale number from the list shown. Accept the Default locale value to instruct the installer to use the system locale as the server locale.

```
Select the locale to be used by the new database cluster.
```

```
Locale
```

```
[1] [Default locale]
[2] C
[3] POSIX
```

```
Please choose an option [1] :
```

When prompted, enter `Y` (or press `Enter` to accept the default value) to install the sample tables and procedures for the database dialect specified by the compatibility mode (Oracle or PostgreSQL):

```
Install sample tables and procedures. [Y/n]:
```

Dynatune functionality allows Advanced Server to make optimal usage of the system resources available on the host machine. To facilitate performance tuning through Dynatune, the installer prompts you first for `Server Utilization` information:

```
Dynatune Dynamic Tuning: Server Utilization
```

```
Please select the type of server to determine the amount of
system resources that may be utilized:
```

```
[1] Development (e.g. a developer's laptop)
[2] General Purpose (e.g. a web or application server)
[3] Dedicated (a server running only EDB Postgres)
```

```
Please choose an option [2] :
```

The `edb_dynatune` configuration parameter determines how Advanced Server allocates system resources. Your selection will establish the initial value of `edb_dynatune`.

- Specify `Development` to set the value of `edb_dynatune` to `33`. A low value dedicates the least amount of the host machine's resources to the database server. This is a good choice for a development machine.
- Specify `General Purpose` to set the value of `edb_dynatune` to `66`. A mid-range value dedicates a moderate amount of system resources to the database server. This would be a good setting for an application server with a fixed number of applications running on the same host as Advanced Server.
- Specify `Dedicated` to set the value of `edb_dynatune` to `100`. A high value dedicates most of the system resources to the database server. This is a good choice for a dedicated server host.

Enter a value of `1`, `2`, or `3`, or accept the default value of `2` (to indicate that the server will be used for `General Purpose` processing) and press `Enter` to continue.

Next, the Advanced Server installer prompts for information about the type of workload the system will be processing:

```
Dynatune Dynamic Tuning:
Workload Profile
```

```
Please select the type of workload this server will be used
for:
```

```
[1] Transaction Processing (OLTP systems)
[2] General Purpose (OLTP and reporting workloads)
[3] Reporting (Complex queries or OLAP workloads)
Please choose an option [1] :
```

The installer uses the `Workload Profile` to establish the initial value of the `edb_dynatune_profile` configuration parameter. The `edb_dynatune_profile` parameter controls performance-tuning aspects based on the type of work that the server performs.

- Enter `1` to indicate `Transaction Processing (OLTP systems)` and set the value of `edb_dynatune_profile` to `oltp`. Recommended when Advanced Server is supporting heavy online transaction processing workloads.
- Enter `2` to indicate `General Purpose (OLTP and reporting workloads)` and set the value of `edb_dynatune_profile` to `mixed`. Recommended for servers that provide a mix of transaction processing and data reporting.
- Enter `3` to indicate `Reporting (Complex queries or OLAP workloads)` and set the value of `edb_dynatune_profile` to `reporting`. Recommended for database servers used for heavy data reporting.

After choosing a `Workload Profile`, press `Enter` to continue.

After the installation is complete, you can adjust the values of `edb_dynatune` and `edb_dynatune_profile` by editing the `postgresql.conf` file, located in the `data` directory of your Advanced Server installation, and restarting the server.

For more information about `edb_dynatune` and other performance-related topics, see the *EDB Postgres Advanced Server Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

When the installer continues, it requests Advanced Configuration information for the PgBouncer and pgAgent services.

```
Advanced Configuration
```

```
-----  
PgBouncer Listening Port [6432]:
```

```
-----  
Service Configuration
```

```
Autostart PgBouncer Service [Y/n]:
```

```
Autostart pgAgent Service [Y/n]:
```

```
Update Notification Service [Y/n]:
```

```
The Update Notification Service informs, downloads and  
installs whenever security patches and other updates are  
available for your EDB Postgres Advanced Server  
installation.
```

## PgBouncer

PgBouncer is a lightweight connection pooling utility for Advanced Server. Connection pooling can dramatically reduce processing time and resources for systems maintaining client connections to one or more databases.

Please note: The PgBouncer program stores a list of users and passwords in clear-text form in the following file:

```
/opt/edb/pgbouncer1.7/etc/userlist.txt
```

By default, the file is located in a directory that is accessible only to the cluster owner (by default, `enterprisedb`), but administrators should take note of the file and maintain permissions in a manner that secures the file from untrusted users.

For more information about PgBouncer, visit the project site at:

<http://pgbouncer.projects.postgresql.org/doc/usage.html>

By default, Advanced Server expects PgBouncer to listen on port 6432; provide a Listening Port, or accept the default, and press Enter to continue.

### pgAgent

pgAgent is a job scheduling agent for Postgres, capable of running multi-step batch/shell and SQL tasks on complex schedules. pgAgent also provides background support for the DBMS\_JOB built-in package compatible with Oracle databases.

### Update Notification Service

If enabled, the Update Notification Service notifies you of any available updates and security patches for your installation of Advanced Server.

By default, the installer specifies that Advanced Server should start the services when the system boots; specify n to disable autostart for PgBouncer, pgAgent, and the Update Notification Service, or accept the defaults, and

Press Enter to continue to the Pre Installation Summary:

```
Pre Installation Summary
```

```
Following settings will be used for installation:
```

```
Installation Directory: /opt/edb
Data Directory: /opt/edb/as9.6/data
WAL Directory: /opt/edb/as9.6/data/pg_xlog
Database Port: 5444
Database Superuser: enterprisedb
Operating System Account: enterprisedb
Database Service: edb-as-9.6
PgBouncer Listening Port: 6432
```

```
Press [Enter] to continue:
```

The Pre Installation Summary lists the options specified during the installation setup process; review the listing and press Enter to continue; press Enter again to start the installation process.

```
Setup is now ready to begin installing EDB Postgres
Advanced Server on your computer.
```

```
Do you want to continue? [Y/n]:
```

The installer extracts the Advanced Server files and proceeds with the installation:

## EDB Postgres Advanced Server Installation Guide

Please wait while Setup installs EDB Postgres Advanced Server on your computer.

```
Installing EDB Postgres Advanced Server
0% _____ 50% _____ 100%
#####
```

The dialog lists each module as it is being installed:

```
Installing EDB Postgres Advanced Server ...
Installing EDB Postgres Advanced Server pgAgent ...
Installing EDB Postgres Connectors ...
Installing EDB Postgres Migration Toolkit ...
Installing EDB Postgres Advanced Server EDB*Plus ...
Installing EDB Postgres Advanced Server Infinite Cache ...
Installing EDB Postgres pgAdmin 4 ...
Installing EDB Postgres Advanced Server Slony Replication
...
Installing EDB Postgres pgPool-II ...
Installing EDB Postgres pgPool-II Extensions ...
Installing EDB Postgres pgBouncer ...
Installing EDB Postgres StackBuilder Plus ...
```

Then, informs you when the installation is complete.

Setup has finished installing EDB Postgres Advanced Server on your computer.




## 4.4.2 Performing an Unattended Installation

To specify that the installer should run without user interaction, include the `--mode unattended` command line option. In unattended mode, the installer uses one of the following sources for configuration parameters:

- command line options (specified when invoking the installer)
- parameters specified in an option file
- Advanced Server installation defaults

Unattended installations are supported on both Windows and Linux systems.

You can embed the non-interactive Advanced Server installer within another application installer; during the installation process, a progress bar allows the user to view the progression of the installation (shown in Figure 4.37).



*Figure 4.37 –The installation progress bar.*

You must have superuser privileges to install Advanced Server using the `--mode unattended` option on a Linux system. On a Windows system, administrative privileges are required. If you are using the `--mode unattended` option to install Advanced Server with another installer, the calling installer must be invoked with superuser or administrative privileges.

To start the installer in unattended mode, specify the `--mode unattended` option on the command line.

### On Linux

To install in unattended mode on a Linux machine, navigate to the directory that contains the Advanced Server installer and enter:


```
./edb-as96-meta-9.6.x.x-linux-x64.run --mode unattended
--superpassword database_superuser_password --webusername
edb_user_name@email.com --webpassword edb_user_password
```

The `--superpassword` option specifies a password for the database superuser. If you omit the option, the database superuser password defaults to `enterprisedb`. The default password can be easily guessed by a potential intruder; be sure to provide a stronger password with the `--superpassword` option.

You must include the `--webusername` and `--webpassword` options to specify the identity of a registered EnterpriseDB user. There is no charge to register for an EnterpriseDB user account; if you do not have an account, you can create one at:

<http://www.enterprisedb.com/user-login-registration>

You can control configuration parameters for Advanced Server by specifying options at the command line, or by including the parameters in a configuration file. Specify the parameters within the configuration file in `option=value` pairs (shown in Figure 4.38).



*Figure 4.38 -A sample configuration parameter file.*

When you invoke the installer, include the `--optionfile` parameter, and the complete path to the configuration parameter file:

```
# ./edb-as96-meta-9.6.x.x-linux-x64.run --optionfile
/~/config_param
```

For more information about the command line options supported during an unattended installation, see Section [4.4.4, Reference - Command Line Options](#).

## On Windows

To start the installer in unattended mode on a Windows system, navigate to the directory that contains the executable file, and enter:

```
edb-as96-meta-9.6.x.x-windows-x64.exe --mode unattended --  
superpassword database_superuser_password --servicepassword  
system_password --webusername edb_user_name@email.com --  
webpassword edb_user_password
```

Include the `--servicepassword` option to specify an operating system password for the user installing Advanced Server. Omitting the option can lead to authentication problems on some Windows systems, and enforced password policies may not accept the default password (`enterprisedb`).

Use the `--webusername` and `--webpassword` options to specify the identity of a registered EnterpriseDB user; if you do not have an account, you can create one at:

<http://www.enterprisedb.com/user-login-registration>

### 4.4.3 Performing an Installation with Limited Privileges

To perform an abbreviated installation of Advanced Server without access to root or administrative privileges, invoke the installer from the command line and include the `--extract-only` option. Invoking the installer with the `--extract-only` option extracts the binary files in an unaltered form, allowing you to experiment with a minimal installation of Advanced Server.

If you invoke the installer with the `--extract-only` options, you can either manually create a cluster and start the service, or run the installation script. To manually create the cluster, you must:

- Initialize the cluster
- Configure the cluster
- Start and stop the service with `pg_ctl`

For more information about the `initdb` and `pg_ctl` commands, please see the PostgreSQL Core Documentation at:

<https://www.postgresql.org/docs/9.6/static/app-initdb.html>

<https://www.postgresql.org/docs/9.6/static/app-pg-ctl.html>

If you include the `--extract-only` option when you invoke the installer, the installer steps through a shortened form of the `Setup` wizard. During the brief installation process, the installer generates an installation script that can be later used to complete a more complete installation. To invoke the installation script, you must have superuser privileges on Linux or administrative privileges on Windows.

The installation script:

- Initializes the database cluster if the cluster is empty.
- Configures the server to start at boot-time.
- Creates services for the supporting components (such as `pgAgent` and `PgBouncer`).
- Establishes initial values for Dynatune (dynamic tuning) variables.

The scripted Advanced Server installation does not create menu shortcuts or access to EDB Postgres StackBuilder Plus, and no modifications are made to registry files. The Advanced Server Update Monitor will not detect components installed by the scripted installation, and will not issue alerts for available updates to those components.

To perform a limited installation and generate an installation script, download and unpack the Advanced Server installer. Navigate into the directory that contains the installer, and invoke the installer with the command:


On Linux:

```
./edb-as96-meta-9.6.x.x-linux-x64.run --extract-only yes
```

On Windows:


```
edb-as96-meta-9.6.x.x-windows.exe --extract-only yes
```

A dialog opens, prompting you to choose an installation language. Select a language for the installation from the drop-down listbox, and click **OK** to continue. The **Setup Wizard** opens (shown in Figure 4.39).




*Figure 4.39 -The Welcome window.*

Click **Next** to continue to the **Advanced Server License Agreement** (shown in Figure 4.40).



*Figure 4.40 -The Advanced Server license agreement.*


After reading the license agreement, select the appropriate radio button and click `Next` to continue to the `User Authentication` window (shown in Figure 4.41).



*Figure 4.41 -The Advanced Server User Authentication window.*

Before continuing, you must provide the email address and password associated with your EnterpriseDB user account. Registration is free; if you do not have a user account, click the link provided to open a web browser, and register your user information.


Enter the email address of a registered account in the `Email` field, and the corresponding password in the `Password` field, and click `Next` to continue.



*Figure 4.42 -The Extract Mode confirmation window.*

The `Extract Mode` window (shown in Figure 4.42) serves as a reminder that this is a limited installation, and as such, Update Monitor will not be able to notify you of available updates for the software included in this installation. Click `Next` to continue to the `Installation Directory` window (shown in Figure 4.43).





*Figure 4.43 -Specify an installation directory.*


On Linux, the default Advanced Server installation directory is:

```
/opt/edb
```

On Windows, the default Advanced Server installation directory is:


```
C:\Program Files\edb
```

You can accept the default installation location, and click `Next` to continue to the `Ready to Install` window (shown in Figure 4.44), or optionally click the `File Browser` icon to choose an alternate installation directory.



*Figure 4.44 -The Setup wizard is ready to install Advanced Server.*


Click `Next` to proceed with the Advanced Server installation.



*Figure 4.45 -Progress bars display the installation progress.*

During the installation, progress bars and popups mark the installation progress (Figure 4.45).

The installer notifies you when the installation with limited privileges is complete (see Figure 4.46).



*Figure 4.46 -The Advanced Server installation is complete.*

After completing the minimal installation, you can execute a script to initialize a cluster and start the service. The script is (by default) located in the following directories:

On Linux:

```
/opt/edb
```

On Windows:

```
C:\Program Files\edb
```

To execute the installation script, open a command line and assume superuser or administrative privileges. Navigate to the directory that contains the script, and execute the command:

On Linux:

```
./runAsRoot.sh
```

On Windows:

```
cscript runAsAdmin.vbs
```

The installation script executes at the command line, prompting you for installation configuration information. The default configuration value is displayed in square braces immediately before each prompt; update the default value or press `Enter` to accept the default value and continue.

### Example

The following dialog is an example of a scripted installation on a Linux system. The actual installation dialog will vary by platform and reflect the options specified during the installation.

```
=====
INSTALLATION DIRECTORY
=====
Please enter the installation directory [ /opt/edb ] :
```

The installation directory is the directory where Advanced Server is installed.

```
=====
DATA DIRECTORY
=====
NOTE: If data directory exists and postgresql.conf file exists in
that directory, we will not initialize the cluster.
```

```
Please enter the data directory path: [ /opt/edb/as9.6/data ] :
```

The data directory is the directory where Advanced Server data is stored.

```
=====
WAL DIRECTORY
=====
Please enter the Write-Ahead Log (WAL) directory path:
  [ /opt/edb/as9.6/data/pg_xlog ] :
```

The WAL directory is where the write-ahead log will be written.

```
=====
DATABASE MODE
=====
Please enter database mode: [ oracle ] :
```

Database mode specifies the database dialect with which the Advanced Server installation is compatible. The optional values are `oracle` or `postgresql`.

## Compatible with Oracle Mode

Specify `oracle` mode to include the following functionality:

- Data dictionary views and data type conversions compatible with Oracle databases.
- Date values displayed in a format compatible with Oracle syntax.
- Oracle-styled concatenation rules (if you concatenate a string value with a `NULL` value, the returned value is the value of the string).
- Schemas (`dbo` and `sys`) compatible with Oracle databases added to the `SEARCH_PATH`.
- Support for the following Oracle built-in packages:

Package	Functionality Compatible with Oracle Databases
<code>dbms_alert</code>	Provides the ability to register for, send and receive alerts.
<code>dbms_crypto</code>	Provides a way to encrypt or decrypt RAW, BLOB or CLOB data.
<code>dbms_job</code>	Implements job-scheduling functionality.
<code>dbms_lob</code>	Provides the ability to manage large objects.
<code>dbms_lock</code>	Provides support for the <code>DBMS_LOCK.SLEEP</code> procedure.
<code>dbms_mview</code>	Provides a way to manage and refresh materialized views.
<code>dbms_output</code>	Provides the ability to display a message on the client.
<code>dbms_pipe</code>	Provides the ability to send a message from one session and read it in another session.
<code>dbms_profiler</code>	Collects and stores performance data about PL/pgSQL and SPL statements.
<code>dbms_random</code>	Provides a way to generate random numbers.
<code>dbms_rls</code>	Implements row level security.
<code>dbms_scheduler</code>	Provides a way to create and manage Oracle-style jobs.
<code>dbms_session</code>	A partial implementation that provides support for <code>DBMS_SESSION.SET_ROLE</code> .
<code>dbms_sql</code>	Implements use of Dynamic SQL
<code>dbms_utility</code>	Provides a collection of misc functions and procedures.
<code>utl_encode</code>	Provides a way to encode or decode data.
<code>utl_file</code>	Provides a way for a function, procedure or anonymous block to interact with files stored in the server's file system.
<code>utl_http</code>	Provides a way to use HTTP or HTTPS to retrieve information found at a URL.
<code>utl_mail</code>	Provides a simplified interface for sending email and attachments.
<code>utl_raw</code>	Provides a way to manipulate or retrieve the length of raw data types.
<code>utl_smtp</code>	Implements smtp email functions.
<code>utl_url</code>	Provides a way to escape illegal and reserved characters in a URL.

This is not a comprehensive list of the compatibility features for Oracle included when Advanced Server is installed in `Compatible with Oracle` mode; more information about Advanced Server is available in the *Database Compatibility for Oracle Developer's Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

If you choose to install in `Compatible with Oracle` mode, the Advanced Server superuser name is `enterprisedb`.

### Compatible with PostgreSQL Mode

Specify `postgresql` to install Advanced Server with complete compatibility with Postgres version 9.6.

For more information about PostgreSQL functionality, see the PostgreSQL Core Documentation available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

If you choose to install in `Compatible with PostgreSQL` mode, the Advanced Server superuser name is `postgres`.

```
====
PORT
====
```

NOTE: We will not be able to examine, if port is currently used by other application.

```
Please enter port: [ 5444 ] :
```

Specify a port number for the Advanced Server listener to listen on.

```
=====
LOCALE
=====
```

```
Please enter the locale: [ DEFAULT ] :
```

Specify a locale for the Advanced Server installation. If you accept the `DEFAULT` value, the locale defaults to the locale of the host system.

```
=====
SAMPLE TABLES
=====
```

```
Install sample tables and procedures? (Y/n): [ Y ] :
```

Press `Return`, or enter `Y` to accept the default, and install the sample tables and procedures; enter an `n` and press `Return` to skip this step.

```
=====
DATABASE SUPERUSER PASSWORD
=====
```

```
Please provide password for the super-user(enterprisedb): [ ] :
Please re-type password for the super-user(enterprisedb): [ ] :
```

Specify and confirm a password for the database superuser. By default, the database superuser is named `enterprisedb`. (On Windows, there is no password validation if you are logged in as an administrator, but you may be prompted to supply a service account password.)

```
=====
SERVER UTILIZATION
=====
```

```
Please enter the server utilization: [ 66 ] :
```

Specify a value between 1 and 100.

The server utilization value is used as an initial value for the `edb_dynatune` configuration parameter. `edb_dynatune` determines how Advanced Server allocates system resources.

- A low value dedicates the least amount of the host machine's resources to the database server; a low value is a good choice for a development machine.
- A mid-range value dedicates a moderate amount of system resources to the database server. A mid-range value is a good setting for an application server with a fixed number of applications running on the same host as Advanced Server.
- A high value dedicates most of the system resources to the database server. This is a good choice for a dedicated server host.

After the installation is complete, you can adjust the value of `edb_dynatune` by editing the `postgresql.conf` file, located in the `data` directory of your Advanced Server installation. After editing the `postgresql.conf` file, you must restart the server for the changes to take effect.

```
=====
WORKLOAD PROFILE
=====
```

```
Please enter the workload profile: [ oltp ] :
```

The workload profile value is used as an initial value for the `edb_dynatune_profile` configuration parameter. `edb_dynatune_profile` controls performance-tuning based on the type of work that the server performs.

- Specify `oltp` if the server will be supporting heavy online transaction workloads.

- Specify `mixed` if the server will provide a mix of transaction processing and data reporting.
- Specify `reporting` if the database server will be used for heavy data reporting.

After the installation is complete, you can adjust the value of `edb_dynatune_profile` by editing the `postgresql.conf` file, located in the `data` directory of your Advanced Server installation, and restarting the server.

Before continuing with the installation, the installer displays the selected options and initializes the database cluster in preparation for the installation of individual components. When the installer has prepared the system for the installation, the installation begins. Before installing a component, the installer prompts you to select modules for installation. With each component, onscreen warnings may alert you to unresolved dependencies.

*Please note that the available components are different for each platform, and the prompts that follow may vary.*

```
Found Slony replication. Do you want to configure Slony?
(Y/n) [ Y ] :
```

Slony facilitates primary-standby replication suited for large databases with a limited number of standby systems.

NOTE: slony replication service is installed. Please configure it as per your requirement and start the service.

```
Found PgBouncer. Do you want to configure PgBouncer? (Y/n)[ Y ] :
```

PgBouncer is a lightweight connection pooling utility for Advanced Server. Connection pooling can dramatically reduce processing time and resources for systems maintaining client connections to one or more databases.

```
=====
PGBOUNCER PORT
=====
```

NOTE: We will not be able to examine, if port is currently used by other application.

```
Please enter the port on which PgBouncer will listen: [ 6432 ] :
```

**Specify a listener port for the PgBouncer utility.**

Starting PgBouncer service...

```
Found Infinite Cache. Do you want to configure Infinite Cache?
(Y/n) [ Y ] :
```



For more information about Infinite Cache and the `edb-icache` daemon, see the *EDB Postgres Advanced Server Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

NOTE: Infinite Cache service is installed. Please configure it as per your requirement and start the service.

Found pgpool-II. Do you want to configure pgpool-II? (Y/n) [Y]:

pgPool-II provides load balancing, connection pooling, high availability, and connection limits for Advanced Server databases.

NOTE: EDBAS-PGPOOL-3.5 SERVICE IS INSTALLED. Please configure it as per your requirement and start the service.

Found EdbPlus. Do you want to configure EdbPlus? (Y/n) [ Y ] :

EDB\*Plus is the Advanced Server command line interface that offers compatibility with Oracle's SQL Plus commands. The installer will prompt you for the absolute path of java on your system; Java 1.7 or higher is required for EDB\*Plus.

Found EdbMtk. Do you want to configure EdbMtk? (Y/n) [ Y ] :

EDB Postgres Migration Toolkit is a command line migration utility that facilitates migration from MySQL, Oracle, Microsoft SQL Server and Sybase databases. The installer will prompt you for the absolute path of java on your system; Java (version 7 or 8) or OpenJDK (version 1.7 or 1.8) is supported by Migration Toolkit.

The installer saves the specified configuration values in the following file:

```
'/opt/edb/.rar_options_XXXXX'
```

After continued processing, the Advanced Server installation on Linux is complete.

#### 4.4.4 Reference - Command Line Options

You can optionally include the following parameters for an Advanced Server installation on the command line, or in a configuration file when invoking the Advanced Server installer.

```
--autostart_pgagent { yes | no }
```

Use the `--autostart_pgagent` parameter to specify whether the installer should start the pgAgent service at boot-time. The default is `yes`.

```
--autostart_pgboncer { yes | no }
```

Use the `--autostart_pgboncer` parameter to specify whether the installer should start the PgBouncer service. The default is `yes`.

```
--create_samples { yes | no }
```

Use the `--create_samples` option to specify whether the installer should create the sample tables and procedures for the database dialect specified with the `--databasemode` parameter. The default is `yes`.

```
--databasemode { oracle | postgresql }
```

Use the `--databasemode` parameter to specify a database dialect. The default is `oracle`.

```
--datadir data_directory
```

Use the `--datadir` parameter to specify a location for the cluster's data directory. *data\_directory* is the name of the directory; include the complete path to the desired directory.

```
--debuglevel { 0 | 1 | 2 | 3 | 4 }
```

Use the `--debuglevel` parameter to set the level of detail written to the *debug\_log* file (see `--debugtrace`). Higher values produce more detail in a longer trace file. The default is `2`.

```
--debugtrace debug_log
```

Use the `--debugtrace` parameter to troubleshoot installation problems. *debug\_log* is the name of the file that contains installation troubleshooting details.

`--disable-components component_list`

Use the `--disable-components` parameter to specify a list of Advanced Server components to exclude from the installation. By default, `component_list` contains '' (the empty string). `component_list` is a comma-separated list containing one or more of the following components:

`dbserver`

EDB Postgres Advanced Server 9.6.

`connectors`

The EDB Postgres Connector API's for JDBC, .NET, OCI and ODBC.

`infinitecache` (Linux only.)

EDB Postgres Advanced Server Infinite Cache allows you to increase the amount of data maintained as in-memory cache by distributing the cache across multiple commodity hardware farms.

`edbmtk`

EDB Postgres Migration Toolkit is a command line migration utility that facilitates migration from MySQL, Oracle, Microsoft SQL Server and Sybase databases.

`pgadmin4` (Linux and Windows only.)

The EDB Postgres pgAdmin 4 provides a powerful graphical interface for database management and monitoring.

`edbplus`

EDB Postgres Advanced Server EDB\*Plus is the Advanced Server command line interface that offers compatibility with Oracle's SQL Plus commands.

`pgpool` (Linux only.)

EDB Postgres pgPool-II provides load balancing, connection pooling, high availability, and connection limits for Advanced Server databases.

`pgpool-extensions`

Include the `pgpool-extensions` option to install server extensions required by the server when running pgPool-II.

`replication`

EDB Postgres Advanced Server Slony Replication facilitates primary-standby replication suited for large databases with a limited number of standby systems.

`pgbouncer`

EDB Postgres PgBouncer is a lightweight connection pooler for Advanced Server that can dramatically reduce the processing time and resources required to maintain a large number of client connections to one or more databases.

`--enable_acledit`

The `--enable_acledit` option instructs the installer to grant permission to the user specified by the `--serviceaccount` option to access the Advanced Server binaries and data directory. The `--enable_acledit` option particularly should be specified when a *discretionary access control list* (DACL) needs to be set for allowing access to objects on a Windows host on which Advanced Server is to be installed. See the following for information on a DACL:

[https://msdn.microsoft.com/en-us/library/windows/desktop/aa446597\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/windows/desktop/aa446597(v=vs.85).aspx)

In order to perform future operations such as upgrading Advanced Server, access to the data directory must exist for the service account user specified by the `--serviceaccount` option. By specifying the `--enable_acledit` option, access to the data directory by the service account user is provided. By default, this option is `false` (disabled).

`--enable-components component_list`

Although this option is listed when you run the installer with the `--help` option, the `--enable-components` parameter has absolutely no effect on which components are installed. All components will be installed regardless of what is specified in `component_list`. In order to install only specific, selected components, you must use the `--disable-components` parameter previously described in this section to list the components you do not want to install.

`--extract-only { yes | no }`

Include the `--extract-only` parameter to indicate that the installer should extract the Advanced Server binaries without performing a complete installation.

Superuser privileges are not required for the `--extract-only` option. The default value is `no`.

`--help`

Include the `--help` parameter to view a list of the optional parameters.

`--installer-language { en | ja | zh_CN | zh_TW | ko }`

Use the `--installer-language` parameter to specify an installation language for Advanced Server. The default is `en`.

`en` specifies English.

`ja` specifies Japanese

`zh_CN` specifies Chinese Simplified.

`zh_TW` specifies Traditional Chinese.

`ko` specifies Korean.

`--install_runtimes { yes | no }` (Windows only.)

Include `--install_runtimes` to specify whether the installer should install the Microsoft Visual C++ runtime libraries. Default is `yes`.

`--locale locale`

Specifies the locale for the Advanced Server cluster. By default, the installer will use to the locale detected by `initdb`.

`--mode {qt | gtk | xwindow | text | unattended}`

Use the `--mode` parameter to specify an installation mode. The following modes are supported:

`qt` - Specify `qt` to tell the installer to use the Qt graphical toolkit

`gtk` - Specify `gtk` to tell the installer to use the GTK graphical toolkit.

`xwindow` - Specify `xwindow` to tell the installer to use the X Window graphical toolkit.

`text` - Specify `text` to perform a text mode installation in a console window. This is a Linux-only option.

`unattended` - Specify `unattended` to specify that the installer should perform an installation that requires no user input during the installation process.

`--optionfile config_file`

Use the `--optionfile` parameter to specify the name of a file that contains the installation configuration parameters. `config_file` must specify the complete path to the configuration parameter file.

`--pgbouncerport`

Use the `--pgbouncerport` parameter to specify a listener port for the PgBouncer service. The default value is `6432`.

`--prefix installation_dir/as9.x`

Use the `--prefix` parameter to specify an installation directory for Advanced Server. The installer will append a version-specific sub-directory (i.e. `as9.6`) to the specified directory. By default, on a Linux system, Advanced Server is installed in:

```
/opt/edb/as9.6
```

The default installation directory on a Windows system is:

```
C:\Program Files\edb\as9.6
```

`--productkey product_key`

Use the `--productkey` parameter to specify a value for the product key.

The `--productkey` parameter is only required when the specified system locale is Japanese, Chinese or Korean.

`--serverport port_number`

Use the `--serverport` parameter to specify a listener port number for Advanced Server.

If you are installing Advanced Server in unattended mode, and do not specify a value using the `--serverport` parameter, the installer will use port `5444`, or the first available port after port `5444` as the default listener port.

`--server_utilization {33 | 66 | 100}`

Use the `--server_utilization` parameter to specify a value for the `edb_dynatune` configuration parameter. The `edb_dynatune` configuration parameter determines how Advanced Server allocates system resources.

- A value of `33` is appropriate for a system used for development. A low value dedicates the least amount of the host machine's resources to the database server.
- A value of `66` is appropriate for an application server with a fixed number of applications. A mid-range value dedicates a moderate amount of system resources to the database server. The default value is `66`.
- A value of `100` is appropriate for a host machine that is dedicated to running Advanced Server. A high value dedicates most of the system resources to the database server.

When the installation is complete, you can adjust the value of `edb_dynatune` by editing the `postgresql.conf` file, located in the `data` directory of your Advanced Server installation. After editing the `postgresql.conf` file, you must restart the server for the changes to take effect.

```
--serviceaccount user_account_name
```

Use the `--serviceaccount` parameter to specify the name of the user account that owns the server process.

- If `--databasemode` is set to `oracle` (the default), the default value of `--serviceaccount` is `enterprisedb`.
- If `--databasemode` is set to `postgresql`, the default value of `--serviceaccount` is set to `postgres`.

Please note that for security reasons, the `--serviceaccount` parameter must specify the name of an account that does not hold administrator privileges.

If you specify both the `--serviceaccount` option and the `--enable_acledit` option when invoking the installer, the database service and pgAgent will use the same service account, thereby having the required permissions to access the Advanced Server binaries and `data` directory. **Note:** For installing on Windows hosts, see the `--enable_acledit` option in this section for additional information relevant to a Windows environment.

Please note that on Windows hosts, if you do not include the `--serviceaccount` option when invoking the installer, the `NetworkService` account will own the database service, and the `pgAgent` service will be owned by either `enterprisedb` or `postgres` (depending on the installation mode).

```
--servicename service_name
```

Use the `--servicename` parameter to specify the name of the Advanced Server service. The default is `edb-as-96`.

```
--servicepassword user_password (Windows only)
```

Use `--servicepassword` to specify the OS system password. If unspecified, the value of `--servicepassword` defaults to the value of `--superpassword`.

```
--superaccount super_user_name
```

Use the `--superaccount` parameter to specify the user name of the database superuser.

- If `--databasemode` is set to `oracle` (the default), the default value of `--superaccount` is `enterprisedb`.
- If `--databasemode` is set to `postgresql`, the default value of `--superaccount` is set to `postgres`.

```
--superpassword superuser_password
```

Use `--superpassword` to specify the database superuser password. If you are installing in non-interactive mode, `--superpassword` defaults to `enterprisedb`.

```
--unattendedmodeui { none | minimal | minimalWithDialogs }
```

Use the `--unattendedmodeui` parameter to specify installer behavior during an unattended installation.

Include `--unattendedmodeui none` to specify that the installer should not display progress bars during the Advanced Server installation.

Include `--unattendedmodeui minimal` to specify that the installer should display progress bars during the installation process. This is the default behavior.

Include `--unattendedmodeui minimalWithDialogs` to specify that the installer should display progress bars and report any errors encountered during the installation process (in additional dialogs).

```
--version
```

Include the `--version` parameter to retrieve version information about the installer:



EDB Postgres Advanced Server 9.6 --- Built on 2016-06-15  
00:04:00 IB: 15.10.1-201511121057

`--webusername {registered_username}`

You must specify the name of a registered user and password when performing an installation of EDB Postgres Advanced Server 9.6. Use the `--webusername` parameter to specify the name of the registered EnterpriseDB user that is performing the installation.

`registered_username` must be an email address.

If you do not have a `registered user name`, visit the EnterpriseDB website at:

<http://www.enterprisedb.com/user-login-registration>

`--webpassword {associated_password}`

Use the `--webpassword` parameter to specify the password associated with the registered EnterpriseDB user that is performing the installation.

`--workload_profile {oltp | mixed | reporting}`

Use the `--workload_profile` parameter to specify an initial value for the `edb_dynatune_profile` configuration parameter. `edb_dynatune_profile` controls aspects of performance-tuning based on the type of work that the server performs.

- Specify `oltp` if the Advanced Server installation will be used to support heavy online transaction processing workloads.
- The default value is `oltp`.
- Specify `mixed` if Advanced Server will provide a mix of transaction processing and data reporting.
- Specify `reporting` if Advanced Server will be used for heavy data reporting.

After the installation is complete, you can adjust the value of `edb_dynatune_profile` by editing the `postgresql.conf` file, located in the `data` directory of your Advanced Server installation. After editing the `postgresql.conf` file, you must restart the server for the changes to take effect.

For more information about `edb_dynatune` and other performance-related topics, see the *EDB Postgres Advanced Server Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation/enterpriseedition>

`--xlogdir` *directory\_name* (Linux only.)

Use the `--xlogdir` parameter to specify a location for the write-ahead log. The default value is `/opt/edb/as9.6/data/pg_xlog`.

## 4.5 Using StackBuilder Plus

The StackBuilder Plus utility provides a graphical interface that simplifies the process of updating, downloading and installing modules that complement your Advanced Server installation. When you install a module with StackBuilder Plus, StackBuilder Plus automatically resolves any software dependencies.

Please note: If your installation resides on a Linux system, you must install the `redhat-lsb` package before invoking StackBuilder Plus. For more information, see Section [4.1](#).

You can invoke StackBuilder Plus at any time after the installation has completed by selecting the StackBuilder Plus menu option from the EDB Add-ons menu (Linux) or from the Apps menu (Windows). Enter your system password (if prompted), and the StackBuilder Plus welcome window opens (shown in Figure 4.63).




Figure 4.63 -The StackBuilder Plus welcome window.

Use the drop-down listbox on the welcome window to select your Advanced Server installation.

StackBuilder Plus requires Internet access; if your installation of Advanced Server resides behind a firewall (with restricted Internet access), StackBuilder Plus can download program installers through a proxy server. The module provider determines if

the module can be accessed through an HTTP proxy or an FTP proxy; currently, all updates are transferred via an HTTP proxy and the FTP proxy information is not used.

If the selected Advanced Server installation has restricted Internet access, use the `Proxy Servers` button on the `Welcome` window to open the `Proxy servers` dialog (shown in Figure 4.64).




Figure 4.64 –The Proxy servers dialog.

Enter the IP address and port number of the proxy server in the `HTTP proxy` on the `Proxy servers` dialog. Currently, all StackBuilder Plus modules are distributed via HTTP proxy (FTP proxy information is ignored). Click `OK` to continue.





Figure 4.65 –The StackBuilder Plus module selection window.

When you have made your selections, click the `Next` button to continue. The tree control on the StackBuilder Plus module selection window (shown in Figure 4.65) displays a node for each module category.

- If the module is installed, you will see the word `(installed)` to the right of the module name.
- If a module name is in **bold** type, the installer has detected a mismatch between the available version and the installed version.
- Boxes next to the modules that are already installed, but eligible for update are automatically checked.


To add new modules to the selected Advanced Server installation, check the box to the left of the module name and click `Next`. A window opens, requesting your EnterpriseDB registration information (as shown in Figure 4.66).



*Figure 4.66 –The User Authentication window.*

Before downloading and installing modules and updates with StackBuilder Plus, you must enter the user information associated with your EnterpriseDB account. If you do not have an EnterpriseDB user account, click the link provided to open a web browser, and enter your user information.

Enter the email address of a registered account in the `Email` field, and the corresponding password in the `Password` field, and click `Next` to continue. The next dialog confirms the packages selected (Figure 4.67).



*Figure 4.67 -A summary window displays a list of selected packages.*

By default, the selected package installers are downloaded to:


On Windows:

```
C:\Users\Administrator
```

On Linux:


```
/root
```

You can change the directory; use the button (...) to the right of the `Download directory` field to open a file selector, and choose an alternate location to store the downloaded installers. Click `Next` to connect to the server and download the required installation files. (see Figure 4.68).



*Figure 4.68 -StackBuilder Plus is downloading installation files for the specified packages.*

When the download completes, a window opens that confirms the installation files have been downloaded and are ready for installation (see Figure 4.69).



*Figure 4.69 -Confirmation that the download process is complete.*

You can check the box next to `Skip Installation`, and select `Next` to exit StackBuilder Plus without installing the downloaded files, or leave the box unchecked and click `Next` to start the installation process.

Each downloaded installer has different requirements. As the installers execute, they may prompt you to confirm acceptance of license agreements, to enter passwords, and enter configuration information.

During the installation process, you may be prompted by one (or more) of the installers to restart your system. Select **No** or **Restart Later** until all installations are completed. When the last installation has completed, reboot the system to apply all of the updates.

You may occasionally encounter packages that don't install successfully. If a package fails to install, StackBuilder Plus will alert you to the installation error with a popup dialog, and write a message to the log file at:

On Windows: %TEMP%

On Linux: /root



Figure 4.70 -StackBuilder Plus confirms the completed installation.

When the installation is complete, StackBuilder Plus will alert you to the success or failure of the installations of the requested packages (see Figure 4.70). If you were prompted by an installer to restart your computer, reboot now.

The following table lists some of the modules supported by StackBuilder Plus. Please note that the list is subject to change and varies by platform.

Category and Module Name	Description
<b>Add-ons, tools and utilities</b>	
EDB*Plus	A SQL*Plus-compatible command-line interface for Advanced Server.



<b>Category and Module Name</b>	<b>Description</b>
EnterpriseDB Migration Toolkit	Migration Toolkit is a command line tool that facilitates migration from Oracle databases into Advanced Server
Infinite Cache	Infinite Cache (for Linux only) allows you to utilize memory on other computers connected to your network to increase the amount of memory in the shared buffer cache.
PgBouncer	Connection pooler for Postgres Server, packaged by EnterpriseDB.
StackBuilder Plus	An advanced application stack builder that provides an easy interface for downloading and installing Advanced Server updates and modules.
pgAgent	pgAgent is a job scheduling agent for Postgres, capable of running multi-step batch/shell and SQL tasks on complex schedules
pgPool-II	pgPool-II provides load balancing, connection pooling, high availability, and connection limits for Advanced Server databases.
<b>Database Drivers</b>	
EnterpriseDB Connectors	A collection of drivers. Includes .NET, ODBC, JDBC and libpq drivers for Advanced Server
<b>Database Server</b>	
Advanced Server	The EDB Postgres Advanced Server database server.
<b>EnterpriseDB Solution Pack</b>	
Postgres Enterprise Manager Agent	The PEM Agent is responsible for executing tasks and reporting statistics from the host and monitored Postgres instances to the PEM Server.
Postgres Enterprise Manager Server	The PEM Server is used as the data repository for monitoring data and as a server to which the agents and client connect.
xDB Replication Server	xDB Replication Server is an asynchronous, primary-to-standby replication system enabling replication of tables from an Oracle or SQL Server database to an Advanced Server database.
<b>Replication Solutions</b>	
Slony Replication	Slony is a primary to multiple standbys replication system that supports cascading and failover. Packaged by EnterpriseDB.
<b>Spatial Extensions</b>	
PostGIS	PostGIS enables Advanced Server to store spatial data for geographic information systems (GIS).
<b>Web Development</b>	
ApachePHP	A distribution of the Apache webserver and PHP, preconfigured for use with Advanced Server. Packaged by EnterpriseDB.

## 4.6 Using the Update Monitor

The Update Monitor utility polls the EnterpriseDB website and alerts you to security updates and enhancements as they become available for Advanced Server 9.6. Update Monitor is automatically installed and invoked with Advanced Server.

When Update Monitor is actively monitoring, the Postgres elephant icon is displayed in the system tray (see Figure 4.71).



Figure 4.71 -The Update Monitor icon.

If you have installed more than one version of Advanced Server, Update Monitor watches for updates and alerts for all installed versions. When Update Monitor finds an update or alert, it displays an alert symbol to let you know that an update or alert is available for one of the Advanced Server installations (see Figure 4.72).



Figure 4.72 -The Update Monitor icon displays an alert.

Right click on the symbol to open the context menu (shown in Figure 4.73).




Figure 4.73 -The Update Monitor context menu.

If updates are available for your Advanced Server installation, the update count is displayed after the View alerts menu item. Click Install components to start the installation process.

A system dialog opens, prompting you to enter your password (Figure 4.74).




Figure 4.74 - Enter a superuser password.

Enter a superuser password, and click OK to continue. StackBuilder Plus opens (shown in Figure 4.75).





Figure 4.75 - The StackBuilder Plus welcome window.

The StackBuilder Plus wizard walks you through installing the latest versions of the Advanced Server component software; see Section [4.5, Using StackBuilder Plus](#) for more information about the update process.

When the update is complete and there are no new updates available, the Update Monitor icon returns to a non-alerted state.

Update Monitor also monitors the EnterpriseDB website for alerts. If an alert is available for your Advanced Server installation, the Update Monitor icon displays an alert symbol. Right-click on the icon to access the context menu, where the alert count is displayed next to the `View alerts` menu item. Choose the `View alerts` option to display the `Postgres Plus Alerts` window (see Figure 4.76).



*Figure 4.76 - An EnterpriseDB alert.*

- The `Postgres Plus Alerts` window displays helpful hyperlinks that can direct you to more information relevant to the alert.
- Use the `Run StackBuilder Plus` button to open `StackBuilder Plus` from the alert to run applicable updates for your current Advanced Server installation.

## 4.7 Installation Troubleshooting

### *Difficulty Displaying Java-based Applications*

If you encounter difficulty displaying Java-based applications (controls or text not being displayed correctly, or blank windows), upgrading to the latest `libxcb-xlib` libraries should correct the problem on most Linux distributions. Please visit the following link for other possible work-arounds:

[http://bugs.sun.com/bugdatabase/view\\_bug.do?bug\\_id=6532373](http://bugs.sun.com/bugdatabase/view_bug.do?bug_id=6532373)

### *--mode unattended Authentication Errors*

Authentication errors from component modules during unattended installations may indicate that the specified values of `--servicepassword` or `--superpassword` may be incorrect.

### *Errors During an Advanced Server Installation on Windows*

If you encounter an error during the installation process on a Windows system, exit the installation, and ensure that your version of Windows is up-to-date. After applying any outstanding operating system updates, re-invoke the Advanced Server installer.

### *Applications Fail to Launch During an Advanced Server Installation on Linux*

If applications fail to launch (such as StackBuilder Plus or your web browser) during the installation process on a Linux system, verify that the `xdg-open` program is on your system. If `xdg-open` is missing, install the `xdg-utils` package.

If you are using the GNOME desktop, load the root profile before running the Advanced Server installation script. To load the root profile, issue the command, `su - root` instead of `su root` before installing Advanced Server.

### *Configuration File Editors Close Spontaneously*

If you are using a Linux system with the `gnome` console, a bug in the `gnome` shell may cause configuration file editors accessed via the Expert Configuration menu (under the Advanced Server Application menu) to close spontaneously. To correct this error, open a terminal window and enter:

```
dconf write /org/gnome/settings-daemon/plugins/cursor/active
false
```

Please note that each time you reboot your system, you must invoke the command, resetting the value.

### ***The Installation Fails to Complete Due to Existing data Directory Contents***

If an installation fails to complete due to existing content in the data directory, the server will write an error message to the server logs:

```
A data directory is neither empty, or a recognisable data
directory.
```

If you encounter a similar message, you should confirm that the data directory is empty; the presence of files (including the system-generated `lost+found` folder) will prevent the installation from completing. Either remove the files from the data directory, or specify a different location for the data directory before re-invoking the installer to complete the installation.

### ***Difficulty Installing the EPEL Release Package***

If you encounter difficulty when installing the EPEL release package, you can use the following command to install the `epel-release` package on RHEL or CentOS 7 platform:

```
yum -y install https://dl.fedoraproject.org/pub/epel/epel-
release-latest-7.noarch.rpm
```

Please note that you may need to enable the `[extras]` repository definition in the `CentOS-Base.repo` file (located in `/etc/yum/repos.d`).

If `yum` cannot access a repository that contains `epel-release`, you will get an error message:

```
No package epel available.
Error: Nothing to do
```

If you receive this error, you can download the EPEL rpm package, and install it manually. To manually install EPEL, download the rpm package, assume superuser privileges, navigate into the directory that contains the package, and install EPEL with the command:

```
yum -y install epel-release
```

# 5 Managing an Advanced Server Installation

Unless otherwise noted, the commands and paths noted in the following section assume that you have performed an installation with the interactive installer.

## 5.1 Starting and Stopping Advanced Server and Supporting Components

A service is a program that runs in the background and requires no user interaction (in fact, a service provides no user interface); a service can be configured to start at boot time, or manually on demand. Services are best controlled using the platform-specific operating system service control utility. Many of the Advanced Server supporting components are services.

The following table lists the names of the services that control Advanced Server and services that control Advanced Server supporting components:

Advanced Server Component Name	Linux Service Name	Windows Service Name
Advanced Server	edb-as-9.6	edb-as-9.6
Infinite Cache	edb-icache	N/A
pgAgent	edb-pgagent-9.6	EDB Postgres Advanced Server 9.6 Scheduling Agent
PgBouncer	edb-pgbouncer-1.7	edb-pgbouncer-1.7
pgPool-II	edb-pgpool-3.5	N/A
Slony	edb-slony-replication-9.6	edb-slony-replication-9.6

Advanced Server's database server, and the services of Advanced Server's supporting components can be controlled at the command line or through operating system-specific graphical interfaces.

## 5.2 Controlling a Service on Linux

The commands that control the Advanced Server service on a Linux platform are version specific.

### 5.2.1 Controlling a Service on CentOS or RHEL 7.x

Advanced Server 9.6 is the first release that is supported on a Linux version that implements the `systemd` service manager. If your installation of Advanced Server resides on version 7.x of RHEL and CentOS, you must use the `systemctl` command to control the Advanced Server service and supporting components.

The `systemctl` command must be in your search path and must be invoked with superuser privileges. To use the command, open a command line, and enter:

```
systemctl action service_name
```

Where:

*action*

*action* specifies the action taken by the service command. Specify:

- `start` to start the service.
- `stop` to stop the service.
- `restart` to stop and then start the service.
- `status` to discover the current status of the service.

*service\_name*

*service\_name* specifies the name of the service.



## 5.2.2 Using `pg_ctl` to Control Advanced Server

You can use the `pg_ctl` utility to control an Advanced Server service from the command line on any platform. `pg_ctl` allows you to start, stop, or restart the Advanced Server database server, reload the configuration parameters, or display the status of a running server. To invoke the utility, assume the identity of the cluster owner, navigate into the home directory of Advanced Server, and issue the command:

```
./bin/pg_ctl -D data_directory action
```

*data\_directory*

*data\_directory* is the location of the data controlled by the Advanced Server cluster.

*action*

*action* specifies the action taken by the `pg_ctl` utility. Specify:

- `start` to start the service.
- `stop` to stop the service.
- `restart` to stop and then start the service.
- `reload` sends the server a SIGHUP signal, reloading configuration parameters
- `status` to discover the current status of the service.

For more information about using the `pg_ctl` utility, or the command line options available, please see the official PostgreSQL Core Documentation available at:

<https://www.postgresql.org/docs/9.6/static/app-pg-ctl.html>

### Choosing Between `pg_ctl` and the `service` Command

You can use the `pg_ctl` utility to manage the status of an Advanced Server cluster, but it is important to note that `pg_ctl` does not alert the operating system service controller to changes in the status of a server, so it is beneficial to use the `service` command whenever possible.

Note that when you invoke the installer with the `--extract-only` option, the installer does not create a service, it merely unpacks the server. If you have installed Advanced

Server by invoking the installer with the `--extract-only` option, you must use the `pg_ctl` command to control the server.

### 5.2.3 Using the edbstart and edbstop Utilities

Note: edbstart and edbstop functionality is supported only on Linux hosts that are running Advanced Server installations performed with the Interactive installer. RPM installations do not support edbstart and edbstop.

While the autostart scripts created during an Advanced Server installation control a single database cluster, the edbstart and edbstop utilities can control multiple database clusters on the same host, with a single configuration file.

The edbstart and edbstop utilities use a file named `edbtab` (described below) to determine which instances of Advanced Server should start when the operating system boots, and stop when the host is shut down.

Before using the edbstart or edbstop utilities, you should disable the Advanced Server autostart scripts. The commands that disable the scripts are platform specific;

on Fedora/Redhat:

```
chkconfig --level 2345 edb-as-9.6 off
```

on Debian/Ubuntu:

```
update-rc.d edb-as-9.6 disable
```

After disabling the Advanced Server service, use an editor to create a file named `edbtab` in the `/etc` directory, or copy the sample file located in:

```
/opt/edb/as9.6/scripts/server/autostart
```

Edit the `edbtab` file, (shown in Figure 5.1) specifying a list of the Advanced Server clusters that the edbstart and edbstop programs will control, and an indicator that designates if the cluster should be automatically started and stopped.




Figure 5.1 - The sample `edbtabs` file.

The `edbtabs` file entry should take the form:

```
edb_home_directory:edb_data_directory:N|Y
```

*edb\_home\_directory*

*edb\_home\_directory* specifies the home directory of the Advanced Server installation that the `edbstart`/`edbstop` utilities will control.

*edb\_data\_directory*

*edb\_data\_directory* specifies the data directory of the database cluster that the `edbstart`/`edbstop` utilities will control. *edb\_data\_directory* is the same as the value of `$PGDATA` for a specified cluster.

N|Y

Y specifies that `edbstart` and `edbstop` should control the service; N specifies that the user will control the service manually.

Include a separate entry in the `edbtabs` file for each Advanced Server cluster that you wish to control with the `edbstart` and `edbstop` utilities.

After editing the `edbtabs` file, copy the `edb_autostart` script to `/etc/init.d`. By default, the `edb_autostart` script is located in:

```
/opt/edb/as9.6/scripts/server/autostart
```

Copy the `edbstart` and `edbstop` scripts to `$EDBHOME`. Make the scripts executable with the following command:

```
chmod +x edbstart
chmod +x edbstop
chmod +x edbstart edbstop /etc/init.d/edb_autostart
```

Enable the `edb_autostart` service with the commands:

```
chkconfig --level 2345 edb_autostart on
chkconfig --add edb_autostart
```

For the service to take effect, you must restart your system.

### **Manually Controlling the Server with `edbstart` and `edbstop`**

You can use `edbstart` and `edbstop` at the command line to manually control all of the clusters specified in the `edbtabs` file, or to control an individual cluster. Call `edbstart` without an argument to start all of the clusters listed within the `edbtabs` file; invoke `edbstop` without an argument to stop all of the clusters listed in the `edbtabs` file. You can control an individual cluster by specifying the cluster's `data` directory as an argument. The following command starts a cluster:

```
edbstart /opt/edb/as9.6/data
```

While the following command stops a cluster:

```
edbstop /opt/edb/as9.6/data
```

## 5.2.4 Configuring Component Services to AutoStart at System Reboot

After installing, configuring and starting the Slony, pgPool-II or Infinite Cache services on a Linux system, you must manually configure your system to autostart the service when your system reboots.

To configure a service to autostart on a Linux system, open a command line, assume superuser privileges, and enter the following command.

On a Redhat-compatible Linux system:

```
/sbin/chkconfig service_name on
```

On a Debian-compatible Linux system, use the command:

```
/usr/sbin/update-rc.d service_name enable
```

Where *service\_name* specifies the name of the service.

Please note that if you are using a Windows system, the Slony service will be configured to autostart by default. On Windows, you can use the `Service Properties` dialog to control the service startup type. For more information about controlling a service on Windows, see Section [5.3](#).

### 5.3 Controlling a Service on Windows

The Windows operating system includes a graphical service controller that offers point-and-click control of Advanced Server and the services associated with Advanced Server components. The service controller simplifies changing the status of a server and configuring server start up behavior.

The Windows Services utility can be accessed through the Administrative Tools section of the Control Panel, or by navigating through the Apps menu to Run; when the Run dialog opens, enter `services.msc` and click OK. When the Services window opens, use the scroll bar to move through the listed services to highlight `edb-as-9.6` (see Figure 5.2).




Figure 5.2 - The Advanced Server service in the Windows Services window.

The Services window shows that the Advanced Server service (`edb-as-9.6`) is currently Running, and has a Startup Type of Automatic.

- Use the `Stop the service` option to stop the instance of Advanced Server. Please note that any user (or client application) connected to the Advanced Server instance will be abruptly disconnected if you stop the service.
- Use the `Start the service` option to start the Advanced Server service.
- Use the `Pause the service` option to tell Advanced Server to reload the server configuration parameters. The `Pause the service` option is an effective way to reset the server parameters without disrupting user sessions for many of the configuration parameters. See Section 6, *Configuring Advanced Server* for more information about the parameters that can be updated with a server reload.

**Note:** A limitation in Windows causes Advanced Server to generate an error message after performing a parameter reload. To confirm that the reload command has successfully updated the parameters, query the `pg_settings` table to verify that the change has taken effect.

- Use the `Restart the service` option to stop and then start the Advanced Server. Please note that any user sessions will be terminated when you stop the service. This option is useful to reset server parameters that only take effect on server start.



### 5.3.1 Controlling Server Startup Behavior on Windows

You can use the Windows Services utility to control the startup behavior of the server. To alter the startup properties of a server, navigate through the Control Panel to the Services window, or navigate through the Apps menu to Run; when the Run dialog opens, enter `services.msc` and click OK.

Right click on the name of the service you wish to change and select Properties from the context menu to open the Properties dialog.

Use the drop-down listbox in the Startup type field (shown in Figure 5.3) to specify how the Advanced Server service will behave when the host starts.




Figure 5.3 - Specifying Advanced Server's startup behavior.

- Specify `Automatic (Delayed Start)` to instruct the service controller to start after boot.
- Specify `Automatic` to instruct the service controller to start and stop the server whenever the system starts or stops.

- Specify `Manual` to instruct the service controller that the server must be started manually.
- Specify `Disabled` to instruct the service controller to disable the service; after disabling the service, you must stop the service or restart the server to make the change take effect. Once disabled, the server's status cannot be changed until `Startup type` is reset to `Automatic (Delayed Start)`, `Automatic` or `Manual`.

## 5.4 Using `initdb` to Create a Cluster

The PostgreSQL `initdb` command creates a database cluster. If you are using the graphical installer to install Advanced Server, the installer will invoke `initdb` to create a cluster for you. If you are using an RPM package to install Advanced Server, you must manually configure the service and invoke `initdb` to create your cluster.

When invoking `initdb`, you can:

- Specify environment options on the command line.
- Use the `systemd` service manager on RHEL or CentOS 7.x and the service configuration file to configure the environment.

For example, to invoke `initdb` on a RHEL or CentOS 7.x system, using the options specified in the service configuration file, assume the identity of the operating system superuser:

```
su - root
```

Then, invoke `initdb`:

```
/usr/edb/as9.6/bin/edb-as-96-setup initdb
```

After creating the cluster, use `systemctl` to start, stop, or restart the service:

```
systemctl { start | stop | restart } edb-as-9.6
```

Advanced Server includes the following `initdb` options that allow you to customize your clusters.

```
--no-redwood-compat
```

Include the `--no-redwood-compat` keywords to instruct the server to create the cluster in PostgreSQL mode. When the cluster is created in PostgreSQL mode, the name of the database superuser will be `postgres`, the name of the default database will be `postgres`, and Advanced Server's features compatible with Oracle databases will not be available to the cluster.

```
--redwood-like
```

Include the `--redwood-like` keywords to instruct the server to use an escape character (an empty string ( ' ')) following the `LIKE` (or PostgreSQL-compatible `ILIKE`) operator in a SQL statement that is compatible with Oracle syntax.

```
--icu-short-form
```

Include the `--icu-short-form` keywords to create a cluster that uses a default ICU (International Components for Unicode) collation for all databases in the cluster. For more information about Unicode collations, please refer to the *EDB Postgres Advanced Server Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

For more information about using `initdb`, see the PostgreSQL Core Documentation available at:

<https://www.postgresql.org/docs/9.6/static/app-initdb.html>

You can also view online help for `initdb` by assuming superuser privileges and entering:

```
/path_to_initdb_installation_directory/initdb --help
```

Where `path_to_initdb_installation_directory` specifies the location of the `initdb` binary file.

## 6 Configuring Advanced Server

If you have performed an installation with an RPM package, you can use your choice of editor to access and modify the configuration files. By default, when installed with a package manager, the configuration files are located in:

```
/var/lib/edb/as9.6/data
```

Unless otherwise noted, the commands and paths noted in the following section assume that you have performed an installation with the interactive installer.

You can easily update parameters that determine the behavior of Advanced Server and supporting components by modifying the following configuration files:

- The `postgresql.conf` file determines the initial values of Advanced Server configuration parameters.
- The `pg_hba.conf` file specifies your preferences for network authentication and authorization.
- The `pg_ident.conf` file maps operating system identities (user names) to Advanced Server identities (roles) when using `ident`-based authentication.

You can use your editor of choice to open a configuration file, or navigate through a menu to open the file:

- On a Windows system, a link to each configuration file is available on the `Apps` menu.

If superuser or administrative privileges are required to edit the file, a dialog opens prompting you for your password.

## 6.1 Modifying the `postgresql.conf` File

Configuration parameters in the `postgresql.conf` file specify server behavior with regards to auditing, authentication, encryption, and other behaviors. The `postgresql.conf` file resides in the `data` directory under your Advanced Server installation.





Figure 6.1 - The `postgresql.conf` file.

Parameters that are preceded by a pound sign (`#`) are set to their default value (as shown in the parameter setting). To change a parameter value, remove the pound sign and enter a new value. After setting or changing a parameter, you must either *reload* or *restart* the server for the new parameter value to take effect.

Within the `postgresql.conf` file, some parameters contain comments that indicate change requires restart. To view a list of the parameters that require a server restart, execute the following query at the EDB-PSQL command line (see Figure 6.2):

```
SELECT name FROM pg_settings WHERE context = 'postmaster';
```



```

root@localhost:/opt/edb/as9.6/bin
File Edit View Search Terminal Help
edb=# SELECT name FROM pg_settings WHERE context = 'postmaster';
      name
-----
allow_system_table_mods
archive_mode
autovacuum_freeze_max_age
autovacuum_max_workers
autovacuum_multixact_freeze_max_age
bonjour
bonjour_name
cluster_name
config_file
data_directory
dbms_alert.max_alerts
dbms_aq.max_databases
dbms_aq.max_pending_retries
dbms_pipe.total_message_buffer
dynamic_shared_memory_type
edb_dynatune
edb_dynatune_profile
edb_enable_icache
edb_max_resource_groups
edb_max_spins_per_delay
event_source
external_pid_file
hba_file
hot_standby
huge_pages
ident_file
listen_addresses
logging_collector
max_connections
max_files_per_process
max_locks_per_transaction
max_pred_locks_per_transaction
max_prepared_transactions
max_replication_slots
max_wal_senders
max_worker_processes
odbc_lib_path
old_snapshot_threshold
oracle_home
port
running_edb_bootstrap_scripts
shared_buffers
shared_preload_libraries
ssl
ssl_ca_file
ssl_cert_file
ssl_ciphers
ssl_crl_file
ssl_ecdh_curve
ssl_key_file
ssl_prefer_server_ciphers
superuser_reserved_connections
track_activity_query_size
track_commit_timestamp
unix_socket_directories
unix_socket_group
unix_socket_permissions
wal_buffers
wal_level
wal_log_hints
(60 rows)

edb=# █

```

Figure 6.2 - Configuration parameters that require a server restart.

If you are changing a parameter that requires a server restart, see Section [5.1](#), *Starting and Stopping Advanced Server* for information about restarting Advanced Server.

On a Linux system, you can reload the system configuration parameter values by navigating through the `EDB Postgres` menu to the `Expert Configuration` menu, and choosing the `Reload Configuration` menu selection. Reloading the configuration parameters does not require Advanced Server users to log out of their current Advanced Server sessions.

On a Windows system, you will find the `Reload Configuration` menu selection on the `Apps` menu.



## 6.2 Modifying the `pg_hba.conf` File

Entries in the `pg_hba.conf` file specify the authentication method or methods that the server will use when authenticating connecting clients. Before connecting to the server, you may be required to modify the authentication properties specified in the `pg_hba.conf` file.

When you invoke the `initdb` utility to create a cluster, `initdb` creates a `pg_hba.conf` file for that cluster that specifies the type of authentication required from connecting clients.

The default authentication configuration specified in the `pg_hba.conf` file is:

```
# TYPE      DATABASE          USER            ADDRESS                 METHOD
# "local" is for Unix domain socket connections only
local      all                all                                md5
# IPv4 local connections:
host       all                all                127.0.0.1/32           md5
# IPv6 local connections:
host       all                all                ::1/128                 md5
# Allow replication connections from localhost, by a user with the
# replication privilege.
#local     replication        enterisedb                md5
#host      replication        enterisedb                127.0.0.1/32           md5
#host      replication        enterisedb                ::1/128                 md5
```

Appropriate authentication methods provide protection and security. Please consult the PostgreSQL documentation for details about authentication options:

<https://www.postgresql.org/docs/9.6/static/auth-methods.html>

To modify the `pg_hba.conf` file, open the file with your choice of editor. After modifying the authentication settings in the `pg_hba.conf` file, use the `services` utility (Windows), or use the following command to restart the server and apply the changes:

On Linux 7.x:

```
systemctl restart edb-as-9.6
```

For more information about modifying the `pg_hba.conf` file, see the PostgreSQL Core Documentation at:

<https://www.postgresql.org/docs/9.6/static/auth-pg-hba-conf.html>

### 6.3 Setting Advanced Server Environment Variables

The graphical installers provide a script that simplifies the task of setting environment variables, allowing a user to more easily invoke client applications at the command line. The script sets the environment variables for your current shell session; when your shell session ends, the environment variables are destroyed. You may wish to invoke `pgplus_env` or `pg_env` from your system-wide shell startup script, so that environment variables are automatically defined for each shell session.

The `pgplus_env` script is created during the Advanced Server installation process and reflects the choices made during installation. To invoke the script, open a command line and enter:

On Linux:

```
source /opt/edb/as9.6/pgplus_env.sh
```

On Windows:

```
C:\Program Files\edb\9.6AS\pgplus_env.bat
```

As the `pgplus_env.sh` script executes (on Linux), it sets the following environment variables:

```
export PATH=/opt/edb/as9.6/bin:$PATH
export EDBHOME=/opt/edb/as9.6
export PGDATA=/opt/edb/as9.6/data
export PGDATABASE=edb
# export PGUSER=enterprisedb
export PGPORT=5444
export PGLOCALEDIR=/opt/edb/as9.6/share/locale
```

As the `pgplus_env.bat` script executes (on Windows), it sets the following environment variables:

```
PATH="C:\Program Files\edb\as9.6\bin";%PATH%
EDBHOME=C:\Program Files\edb\as9.6
PGDATA=C:\Program Files\edb\as9.6\data
PGDATABASE=edb
REM @SET PGUSER=enterprisedb
PGPORT=5444
PGLOCALEDIR=C:\Program Files\edb\as9.6\share\locale
```

If you have used an installer created by EnterpriseDB to install PostgreSQL, the `pg_env` script performs the same function. To invoke the `pg_env` script, open a command line, and enter:

### On Linux:

```
source /opt/PostgreSQL/9.6/pg_env.sh
```

### On Windows:

```
C:\Progra~1\PostgreSQL\9.6\pg_env.bat
```

As the `pg_env.sh` script executes (on Linux), it sets the following environment variables:

```
PATH=/home/opt/PostgreSQL/9.6/bin:$PATH
PGDATA=/home/opt/PostgreSQL/9.6/data
PGDATABASE=postgres
PGUSER=postgres
PGPORT=5432
PGLOCALEDIR=/home/opt/PostgreSQL/9.6/share/locale
MANPATH=$MANPATH:/home/opt/PostgreSQL/9.6/share/man
```

As the `pg_env.bat` script executes (on Windows), it sets the following environment variables:

```
PATH="C:\Program Files\PostgreSQL\9.6\bin";%PATH%
PGDATA=C:\Program Files\PostgreSQL\9.6\data
PGDATABASE=postgres
PGUSER=postgres
PGPORT=5432
PGLOCALEDIR=C:\Program Files\PostgreSQL\9.6\share\locale
```

## 6.4 Connecting to Advanced Server

`psql` is a command line client application that allows you to query the server, and review the query results. Please note that additional configuration steps are required before connecting to an Oracle or MySQL database.

### Connecting to the Database with the `psql` Client

To open the `edb-psql` client, the client must be in your search path. The executable resides in the `bin` directory, under your Advanced Server installation.

On Linux:


```
/opt/edb/as9.6/bin/psql
```

On Windows:

```
C:\Program Files\edb\as9.6\bin\psql
```

Use the following command and command options to start the `psql` client:

```
psql -d edb -U enterprisedb
```



*Figure 6.3 - Connecting to the server.*

Where:

- d specifies the database to which `psql` will connect;
- U specifies the identity of the database user that will be used for the session.

If you have performed an installation with the interactive installer, you can easily access the `psql` client through the Applications or Start menu. Navigate through the EDB Postgres/Advanced Server 9.6 menu to the Run SQL Command Line menu, and select EDB-PSQL. When the Terminal window opens, provide connection information for your session.

For more information about using the command line client, please refer to the PostgreSQL Core Documentation at:

<https://www.postgresql.org/docs/9.6/static/app-psql.html>

## 6.4.1 Connecting to an Oracle or MySQL Database

### Oracle Client Connectivity

Before connecting Advanced Server to an Oracle database, you must download and install the Oracle JDBC driver (`ojdbcxx.jar`) from the Oracle website. You can find a link to the free JDBC driver at:

<https://www.enterprisedb.com/advanced-downloads>

Download the `ojdbcxx.jar` file, where `xx` specifies the version of the driver that is appropriate for your Oracle installation, and place it in the `JAVA_HOME\jre\lib\ext` directory.

### MySQL Client Connectivity

Before connecting Advanced Server to a MySQL database, you must download and install the MySQL JDBC driver (`mysql-connector-java-5.0.8-bin.jar`) from the MySQL website. You can find a link to the free JDBC driver at:

<https://www.enterprisedb.com/advanced-downloads>

Download the `mysql-connector-java-5.0.8-bin.jar` file and place it in the `JAVA_HOME\jre\lib\ext` directory.

# 7 Advanced Server Supporting Components

After installing Advanced Server, you must configure and manually start the services of some supporting components. The following sections list the Advanced Server components that require post-installation configuration, and information about their services.

Please note that you must install a Java environment before invoking EDB\*Plus or Migration Toolkit or before using PL/Java or the JDBC connector.

## 7.1 EDB\*Plus - Configuring an RPM Installation

If you have performed an RPM installation of EDB\*Plus, you must perform the following steps before invoking EDB\*Plus.

### Setting the Session Environment Variables

Before invoking EDB\*Plus on a Linux system, you must set the values of environment variables. Use the following commands to set variable values:

```
export JAVA_HOME=<path_to_java>
export PATH=<path_to_java>/bin:$PATH
```

### Configuring EDB\*Plus Authentication

By default, the `pg_hba.conf` file for the RPM installer enforces IDENT authentication. Before invoking EDB\*Plus, you must either modify the `pg_hba.conf` file, changing the authentication method to a form other than IDENT (and restarting the server), or perform the following steps to ensure that an IDENT server is accessible:

- Confirm that an `identd` server is installed and running. For example, you can use the `yum` package manager to install an `identd` server by invoking the command:

```
yum install xinetd authd
```

The command should create a file named `/etc/xinetd.d/auth` that contains:

```
service auth
{
    disable          = yes
```

```

socket_type      = stream
wait             = no
user             = ident
cps             = 4096 10
instances       = UNLIMITED
server          = /usr/sbin/in.authd
server_args     = -t60 --xerror --os
}

```

Note: if the file includes a `-E` argument at the end of `server_args`, please erase the `-E`.

Then, to start the `identd` server, invoke the commands:

```

systemctl enable xinetd

systemctl start xinetd

```

- Open the `pg_ident.conf` file and create a user mapping:

```

# map_name      system_username  postgres_username
                edbas           enterprisedb      enterprisedb

```

Where:

The name specified in the `map_name` column is a user-defined name that will identify the mapping in the `pg_hba.conf` file.

The name specified in the `system_username` column is `enterprisedb`.

The name specified in the `postgres_username` is `enterprisedb`.

- Open the `pg_hba.conf` file and modify the IDENT entries.

If you are using an IPv4 local connection, modify the file entry to read:

```

host all all 127.0.0.0/0 ident map=edbas

```

If you are using an IPv6 local connection:

```

host all all ::1/128 ident map=edbas

```

- Restart the Advanced Server service before invoking EDB\*Plus.

## 7.2 Infinite Cache

Unless otherwise noted, the commands and paths noted in the following section assume that you have performed an installation with the interactive installer.

Please note that Infinite Cache has been deprecated and may be removed in a future release. Please contact your EnterpriseDB Account Manager or <mailto:sales@enterprisedb.com> for more information.

Infinite Cache allows Linux systems to utilize memory on other computers connected to their network to increase the amount of memory in the shared buffer cache. For more information about Infinite Cache functionality, please refer to the *EDB Postgres Advanced Server Guide* available from the EnterpriseDB website at:

<http://www.enterprisedb.com/products-services-training/products/documentation/enterpriseedition>

After installing Advanced Server, you must provide configuration information for Infinite Cache, and start the service. You must:

- Specify Infinite Cache server settings in the Infinite Cache configuration file.

Modify the Advanced Server `postgresql.conf` file, enabling Infinite Cache, and specifying connection and compression settings.

Start the Infinite Cache service.

The Infinite Cache configuration file is named `edbas-icache`, and contains two parameters and their associated values:

Parameter	Description	Default Value
PORT	The <code>PORT</code> variable specifies the port on which Infinite Cache listens for connections from the server.	11211
CACHESIZE	The <code>CACHESIZE</code> variable specifies the default cache size (in mega-bytes)	500

By default, the file is located in the `/opt/edb/icache/etc` directory. To modify a parameter value, open the `edbas-icache` file with your editor of choice, and edit the parameter values.

To enable Infinite Cache, you must modify the `postgresql.conf` file, setting the values of the configuration parameters that control the behavior of Infinite Cache. To modify a parameter, open the `postgresql.conf` file (located in the `data` directory, under your Advanced Server installation), and locate the section of the configuration file shown below:



```
# - InfiniteCache
#edb_enable_icache = off
#edb_icache_servers = '' #'host1:port1,host2,ip3:port3,ip4'
#edb_icache_compression_level = 6
```

Within the `postgresql.conf` file, lines that begin with a pound sign (#) are treated as a comment; to edit a given parameter, remove the pound sign and specify a value for the parameter. When you've updated and saved the configuration file, restart the database server for the changes to take effect.

Parameter	Description
<code>edb_enable_icache</code>	Use the <code>edb_enable_icache</code> parameter to enable or disable Infinite Cache. When <code>edb_enable_icache</code> is set to on, Infinite Cache is enabled; if the parameter is set to off, Infinite Cache is disabled. If you enable Infinite Cache, you must use the <code>edb-icache_servers</code> parameter to specify a list of cache servers. The default value is <code>off</code> .
<code>edb_icache_servers</code>	Use the <code>edb_icache_servers</code> parameter to specify a list of one or more servers with active <code>edb-icache</code> daemons. Specify a string value that takes the form of a comma-separated list of <code>hostname:port</code> pairs. You may specify a maximum of 128 cache nodes.
<code>edb_icache_compression_level</code>	<code>edb_icache_compression_level</code> controls the compression level that is applied to each page before storing it in the distributed cache. The parameter must be greater than or equal to 0 or less than or equal to 9. A compression level of 0 disables compression, while a compression level of 9 invokes the maximum amount of compression. By default, this parameter is set to 6.

The following example shows a typical collection of Infinite Cache settings:

```
edb_enable_icache = on
edb_icache_servers =
'localhost,192.168.2.1:11200,192.168.2.2'
edb_icache_compression_level = 6
```

After specifying configuration options, you must start the Infinite Cache service. Before starting the service, ensure that the `edb-icache` daemons are running on each server specified in `edb_icache_servers` parameter.

The Infinite Cache service script is named `edbas-icache`. The service script resides in the `/etc/init.d` directory. For detailed information about stopping or starting a service on your platform, please see [Section 5](#).

## 7.3 Language Pack

Language Pack installers contain supported languages that may be used with the Advanced Server and PostgreSQL database installers. The Language Pack installer allows you to create languages for PL/Perl, PL/Tcl, and PL/Python without installing supporting software from third party vendors.

The Language Pack installer includes:

- Tcl with TK, version 8.5
- Perl, version 5.20
- Python, version 3.3

You can use StackBuilder Plus to invoke the Language Pack installer. For information about using StackBuilder Plus, see Section [4.5](#).

The Perl package contains the `cpan` package manager, and Python contains `pip` and `easy_install` package managers. There is no package manager for Tcl/TK.

### Configuring Language Pack on Linux

On Linux, the installer places the languages in:

```
/opt/edb/languagepack-9.6/
```

If you install Language Pack before Advanced Server, the Advanced Server installer will detect the Language Pack installation, and set the paths in the `plLanguages.config` file for you.

If you are invoking the Advanced Server installer using the `--extract-only` option, or if you install Language Pack after installing Advanced Server, you must manually configure the installation. The Language Pack configuration file is named:

```
/opt/edb/as9.6/etc/sysconfig/plLanguages.config
```

If you are installing Language Pack on a system that already hosts an Advanced Server installation, use your editor of choice to modify the `plLanguages.config` file, and modify the entries to include the locations of each language:

```
EDB_PERL_VERSION=5.20
EDB_PYTHON_VERSION=3.3
EDB_TCL_VERSION=8.5
```

```
EDB_PERL_PATH=/opt/edb/languagepack-9.6/Perl-5.20
EDB_PYTHON_PATH=/opt/edb/languagepack-9.6/Python-3.3
EDB_TCL_PATH=/opt/edb/languagepack-9.6/Tcl-8.5
```

After modifying the `plLanguages.config` file, restart the server for the changes to take effect. See Section 5 for detailed information about restarting the server.

## Configuring Language Pack on Windows

On Windows, the Language Pack installer places the languages in:

```
C:\edb\languagepack-9.6\x64
```

After installing Language Pack, you must set the following variables:

```
set PYTHONHOME=C:\edb\languagepack-9.6\x64\Python-3.3
```

Use the following commands to add Python, Perl and Tcl to your search path:

```
set PATH= C:\edb\LanguagePack-9.6\x64\Python-3.3\bin:
C:\edb\LanguagePack-9.6\x64\Perl-5.20\bin:
C:\edb\LanguagePack-9.6\x64\Tcl-8.5\bin;%PATH%
```

After setting the system-specific steps required to configure Language Pack on Windows, restart the Advanced Server database server; see Section 5 for detailed information about restarting the server.

## Configuring Language Pack on OSX

If you are installing Language Pack on a PostgreSQL host on OSX, the Language Pack installer places the languages in:

```
/Library/PostgreSQL/LanguagePack/9.6
```

After installing Language Pack, you must set the following variables:

```
export PERLHOME=/Library/PostgreSQL/LanguagePack/9.6/Perl-5.20
export PYTHONHOME=/Library/PostgreSQL/LanguagePack/9.6/Python-3.3
export TCLHOME=/Library/PostgreSQL/LanguagePack/9.6/Tcl-8.5
```

Use the following commands to add Python, Perl and Tcl to your search path:

```
export PATH=$PYTHONHOME/bin:$PERLHOME/bin:$TCLHOME/bin:$PATH
export DYLD_LIBRARY_PATH=$PYTHONHOME/lib:$DYLD_LIBRARY_PATH
export DYLD_LIBRARY_PATH=$PERLHOME/lib/CORE:$DYLD_LIBRARY_PATH
export DYLD_LIBRARY_PATH=$TCLHOME/lib:$DYLD_LIBRARY_PATH
```

After performing the system-specific steps required to configure Language Pack on OSX, restart the database server.

**Known Language Pack Restrictions:**

- The current set of installers can only be installed in a fixed location. The packages are not relocatable.

There is no package manager for Tcl.

The installer will only extract in the stated installation path.

**Known Bugs:**

- On Windows, the `pythonw.exe`, `pyw.exe` and other binaries may produce an error, reporting fault module in a `MSVCR120.dll`.

## 7.4 Migration Toolkit - Configuring an RPM Installation

Please note that you must install a Java environment before invoking Migration Toolkit. Migration toolkit is supported on Java (versions 7 or 8) or OpenJDK (versions 1.7 or 1.8).

If you have performed an RPM installation of Migration Toolkit, you must perform the following steps before invoking Migration Toolkit.

### Using Migration Toolkit with IDENT Authentication

By default, the `pg_hba.conf` file for the RPM installer enforces IDENT authentication for remote clients. Before invoking Migration Toolkit, you must either modify the `pg_hba.conf` file, changing the authentication method to a form other than IDENT (and restarting the server), or perform the following steps to ensure that an IDENT server is accessible:

- Confirm that an `identd` server is installed and running. For example, you can use the `yum` package manager to install an `identd` server by invoking the command:

```
yum install xinetd authd
```

The command should create a file named `/etc/xinetd.d/auth` that contains:

```
service auth
{
    disable          = yes
    socket_type      = stream
    wait             = no
    user             = ident
    cps              = 4096 10
    instances        = UNLIMITED
    server           = /usr/sbin/in.authd
    server_args      = -t60 --xerror --os
}

```

Note: if the file includes a `-E` argument at the end of `server_args`, please erase the `-E`.

Then, to start the `identd` server, invoke the commands:

```
systemctl enable xinetd
systemctl start xinetd
```

- Open the `pg_ident.conf` file and create a user mapping:

```
# map_name    system_username  postgres_username
    edbas      enterprisedb    enterprisedb
```

Where:

The name specified in the `map_name` column is a user-defined name that will identify the mapping in the `pg_hba.conf` file.

The name specified in the `system_username` column is `enterprisedb`.

The name specified in the `postgres_username` is `enterprisedb`.

- Open the `pg_hba.conf` file and modify the IDENT entries.

If you are using an IPv4 local connection, modify the file entry to read:

```
host all all 127.0.0.0/0 ident map=edbas
```

If you are using an IPv6 local connection:

```
host all all ::1/128 ident map=edbas
```

- Restart the Advanced Server service before invoking Migration Toolkit.

For more information about using Migration Toolkit, see the *EDB Postgres Migration Toolkit Guide* available at:

<http://www.enterprisedb.com/products-services-training/products/documentation>

## 7.5 *pgAgent*

EDB Postgres Advanced Server Scheduling Agent (*pgAgent*) is a job scheduling agent for Advanced Server. When you schedule a *pgAgent* job, the scheduling agent records the job definition in a scheduling table. The *pgAgent* service (running in the background) monitors the scheduling table and executes jobs at their scheduled time.

The Advanced Server installer creates the scheduling tables required by the *pgAgent* service. If you are installing Advanced Server in `Compatible with Oracle mode` (the default), the scheduling tables are created in the `edb` database; if you are installing in `Compatible with PostgreSQL mode`, the tables are created in the `postgres` database.

You can use the EDB Postgres Enterprise Manager Client (PEM), available from EnterpriseDB, to conveniently schedule and manage *pgAgent* jobs. Before using *pgAgent*, you must create the *pgAgent* extension in each database in which you wish to schedule jobs. To install the *pgAgent* schema, you must:

- Use your choice of client (for example, `pgAdmin 4` or `psql`) to connect to the database in which you wish to create the extensions.
- Invoke the command:

```
CREATE EXTENSION pgagent;
```

For detailed usage information about *pgAgent*, please see the online help made available by `pgAdmin 4` (accessible through the EDB Postgres `Start` or `Apps` menu).



## 7.6 PgBouncer

Unless otherwise noted, the commands and paths noted in the following section assume that you have performed an installation with the interactive installer.

PgBouncer is a lightweight connection pooler for Advanced Server. During an Advanced Server installation, the Advanced Configuration window will offer you the opportunity to specify a PgBouncer Listening Port, and allow you to specify a PgBouncer autostart preference. By default, PgBouncer is configured to monitor port 6432, and to start automatically when the operating system starts.

### Configuring PgBouncer

When the PgBouncer service is running, any Postgres client connecting to the PgBouncer listener port specified in the configuration file will use connection pooling. PgBouncer connection and configuration information is stored in the `pgbouncer.ini` file, located in the following directory:

On Linux:

```
/opt/edb/pgbouncer-1.7/share/
```

On Windows:

```
C:\Program Files\edb\pgbouncer-1.7\share
```

The PgBouncer configuration file is divided into two sections: `[databases]` and `[pgbouncer]`.

The `[databases]` section of the configuration file contains a list of databases and the associated connection information; in an Advanced Server installation, the configuration file contains an entry for the installation of Advanced Server that installed PgBouncer:

```
edb = host=127.0.0.1 port=5444
```

You can specify additional database connection information in the configuration file in the form of `keyword=value` pairs. You can include the following parameters:

Parameter	Description
<code>name</code>	The name of the database to which the client application will connect.
<code>host</code>	The IP address of the host.
<code>port</code>	The port on which the host is listening.
<code>dbname</code>	The (optional) database name.
<code>user</code>	A username (if different than the information specified by the connecting client).
<code>password</code>	A password (if different than the information specified by the connecting client).

The following example demonstrates the syntax allowed in the `[databases]` section of the configuration file:

```
[databases]
edb = host=127.0.0.1 port=5444
acctg = host=192.168.10.101 port=5432 user=lola
password=1safe_pwd!
```

Include the `dbname` parameter to map the connection name to an alternate database name. For example:

```
hr = host=127.0.0.1 port=5444 dbname=humanresources
```

Please note that the connection information will vary according to the platform, client software and identity you are connecting with. PgBouncer uses the information provided in the connection string to connect to the database server. Specifying a user in the `pgbouncer.ini` file overrides user details supplied by the client. If the client provides user information, that information is used to connect to PgBouncer, which in turn uses the information specified in the PgBouncer configuration file to connect to the server. The details of the user specified in the configuration file must be defined in the database cluster.

Note: If you do not specify user details in `pgbouncer.ini`, the username and password will be authenticated by the database server and PgBouncer. As such, the username and password should be included in the `userlist.txt` file and the database cluster.

The `[pgbouncer]` section of the configuration file contains configuration details specific to PgBouncer:

Parameter	Description
<code>admin_users</code>	A comma-delimited list of users that are allowed to access the Admin Console (for management and monitoring purposes). By default, PgBouncer is installed with an <code>admin_users = enterprisedb</code> .
<code>auth_file</code>	The path to the authentication file that contains username and passwords of clients that may connect to PgBouncer. The authentication file ( <code>userlist.txt</code> ) is located in <code>/opt/edb/pgbouncer-1.7/etc</code> , and contains <code>username/password</code> pairs that specify the identities that clients may use to access PgBouncer. Within the authentication file, the username and password must be specified within double-quotes, as shown below:  <pre>"user_name" "password"</pre> To make changes to the identities that can access PgBouncer, you can edit the existing authentication file, or specify an alternate authentication file with the <code>auth_file</code> parameter. <b>auth_type</b>
<code>auth_type</code>	The authentication method used by PgBouncer. May be: <code>md5</code> , <code>crypt</code> , <code>plain</code> , <code>trust</code> or <code>any</code> . The default value is <code>md5</code> .

<code>default_pool_size</code>	The amount of user connections that are allowed to access the server. The default is 20 active connections.
<code>group_connections</code>	Clients providing the same <code>application_name</code> will be grouped to use the same connection. The default is 0.
<code>ignore_startup_parameters</code>	A comma-delimited list of application startup packets that PgBouncer should ignore. The default is <code>application_name</code> .
<code>listen_addr</code>	The IP address on which PgBouncer listens for client connections. If omitted, only Unix socket connections are allowed; the client must also reside on the same host as PgBouncer and may not specify a host IP address when connecting to PgBouncer.
<code>listen_port</code>	The port that PgBouncer monitors for client connections. By default, PgBouncer listens on port 6432.
<code>logfile</code>	The path to the PgBouncer log file.
<code>max_client_conn</code>	The maximum number of connections allowed. The default is 100.
<code>pidfile</code>	The path to the process ID file.
<code>pool_mode</code>	The value of <code>pool_mode</code> specifies when the server connection can be made available to the connection pool. May be: <code>session</code> , <code>transaction</code> or <code>statement</code> . The default value is <code>session</code> .
<code>server_reset_query</code>	The default is <code>DISCARD ALL</code> which instructs PgBouncer to clean any changes made to a database session.
<code>stats_users</code>	A comma delimited list of users who are allowed to connect and run read-only queries. The default is <code>stats_users = enterprisedb</code> .

The following example demonstrates the syntax allowed in the `[pgbouncer]` section of the configuration file:

```
[pgbouncer]
logfile = /var/log/edb/pgbouncer1.7/edb-pgbouncer-1.7.log
pidfile = /var/run/edb/pgbouncer1.7/edb-pgbouncer-1.7.pid
listen_addr = *
listen_port = 6432
auth_type = md5
auth_file = /opt/edb/pgbouncer-1.7/etc/userlist.txt
admin_users = enterprisedb
stats_users = enterprisedb
pool_mode = session
server_reset_query = DISCARD ALL
ignore_startup_parameters = application_name
max_client_conn = 100
default_pool_size = 20
group_connections = 0
```

For more information about the settings used in the `pgbouncer.ini` file, please visit:

<https://pgbouncer.github.io/config.html>

After editing the PgBouncer configuration file to reflect your environment, you must restart the PgBouncer service for the changes to take effect. For detailed information about controlling the PgBouncer service, see Section 5.

## Using the PgBouncer Admin Console

The Admin Console allows you to retrieve statistical information about PgBouncer activity, and to control the PgBouncer process. You can use the `edb-psql` client to access the PgBouncer Admin Console by connecting to the `pgbouncer` database. The following example connects to the `pgbouncer` database with the `edb-psql` client on a Linux system. PgBouncer is listening on port `6432`, with a user name of `enterprisedb`:

Enter following command after navigating to the `bin` directory under your Advanced Server installation:

```
# ./psql -p 6432 -U enterprisedb pgbouncer
```

Please note that the required connection information will vary according to the connecting client, platform and authentication information required by the server.

After connecting to the `pgbouncer` database, you can use the `SHOW CLIENTS` command to retrieve client-related information:

```
# SHOW CLIENTS;
```

The `SHOW CLIENTS` command returns:

```
--[ RECORD 1 ]--+-+-----
type           | C
user            | postgres
database       | pgbouncer
state          | active
addr           | unix
port           | 6432
local_addr     | unix
local_port     | 6432
connect_time   | 2010-05-25 05:26:20
request_time   | 2010-05-25 05:39:46
ptr            | 0x8655d20
link           |
```

You can use other variations of the `SHOW` command to retrieve information about PgBouncer:

```
SHOW STATS
SHOW SERVERS
SHOW POOLS
SHOW LISTS
SHOW USERS
SHOW DATABASES
SHOW FDS
```

SHOW CONFIG

You can use the following commands to control the PgBouncer process:

PAUSE

Use the `PAUSE` command to disconnect all servers after waiting for current queries to complete.

SUSPEND

Use the `SUSPEND` command to flush the socket buffers and suspend the PgBouncer process.

RESUME

Use the `RESUME` command to resume work after a `PAUSE` or `SUSPEND` command.

SHUTDOWN

Use the `SHUTDOWN` command to stop the PgBouncer process and exit.

RELOAD

Use the `RELOAD` command to reload the PgBouncer configuration files.

For more information about using PgBouncer, visit:

<http://pgbouncer.projects.pgfoundry.org/doc/usage.html>

## 7.7 *pgPool-II*

Unless otherwise noted, the commands and paths noted in the following section assume that you have performed an installation with the interactive installer.

The *pgPool-II* utility package acts as a middleman between client applications and Server database servers. *pgPool-II* functionality is transparent to client applications; client applications connect to *pgPool-II* instead of directly to Advanced Server, and *pgPool-II* manages the connection. EnterpriseDB supports the following *pgPool-II* features:

- Load balancing
- Connection pooling
- High availability
- Connection limits

*pgPool-II* runs as a service on Linux systems, and is not supported on Windows systems. *pgPool-II* functionality is controlled via configuration parameter settings made in the configuration files. If you have used the graphical installer, sample configuration files are located in:

```
/opt/edb/pgpool-3.5/etc/pgpool.conf.sample
/opt/edb/pgpool-3.5/etc/pool_hba.conf.sample
/opt/edb/pgpool-3.5/etc/pcp.conf.sample
```

If you have used an RPM package to install *pgPool-II*, the configuration files are located in:

```
/etc/sysconfig/edb/pgpool3.5/pgpool.conf.sample
/etc/sysconfig/edb/pgpool3.5/pool_hba.conf.sample
/etc/sysconfig/edb/pgpool3.5/pcp.conf.sample
```

After modifying the parameter settings that implement *pgPool-II* functionality for your installation, you must restart the *pgPool-II* service. For detailed information about controlling the *pgPool-II* service, see Section [5](#).

Please note that the configuration options for *pgPool-II* are extensive; the options listed below should be considered a starting point only. For more information about configuring and using *pgPool-II*, please consult the project website at:

[http://www.pgpool.net/mediawiki/index.php/Main\\_Page](http://www.pgpool.net/mediawiki/index.php/Main_Page)

## pgPool-II Host Setup

When pgPool-II starts, it records its process ID in a file whose name is determined by the `pid_file_name` configuration parameter. The initial value of the `pid_file_name` parameter in the sample file is:

```
pid_file_name = '/var/run/edb/pgpool3.5/edb-pgpool-3.5.pid'
```

Please note that the contents of the `/var/run` directory (including the `pgpool` directory) may be removed by the operating system during a reboot. The `/var/run/pgpool` directory should NOT be used as the location for the `pgpool.pid` file.

## Configuring Connection Pooling

pgPool-II provides a set of child processes that maintain cached connections to one or more database servers. When a client connects, pgPool-II attempts to reuse a connection from its pool, thus avoiding the overhead of opening and closing client connections.

A connection in the pool can be reused only if the target database and the connection user match a prior connection that is currently in the pool. Connection pooling configuration options (such as the number of child processes, and the maximum number of cached connections per child) are specified in the `pgpool.conf` file.

To configure connection pooling with one database server:

- Configure the `pg_hba.conf` file on the pgPool-II host to permit connections between the clients and the server.

Copy the `pgpool.conf.sample` file to `pgpool.conf`, and modify the file, setting the `connection_cache` parameter to `on`, and specifying connection properties for your database server.

For example:

```
connection_cache = on
backend_hostname0 = 'localhost'
backend_port0 = 5444
backend_weight0 = 1
backend_data_directory0 = '/opt/edb/as9.6/data'
```

Note that in the `pgpool.conf` file, connection parameters have an appended digit that specifies a cluster node identifier. Database node `0` specifies values for the primary node.

Optionally, configure pgPool-II client authentication.

Optionally, configure the PCP administrative interface.

Start pgPool-II and begin using your application.

## Configuring Streaming Replication and pgPool-II Load Balancing

EnterpriseDB supports replication scenarios that use pgPool-II load balancing with PostgreSQL streaming replication or Slony replication. The supported replication methods ensure that database updates made by client applications are applied to multiple backend servers. For detailed information about the benefits of each replication method and detailed configuration instructions, please review project documentation for each utility.

When load balancing is enabled, pgPool-II distributes some types of `SELECT` statements to backend servers, allowing multiple database servers and hosts to share the processing load of `SELECT` statements issued by client applications.

When configuring pgPool-II load balancing, it is crucial that the initial database environments in all backend servers are identical:

- Tables must have the same name, definition, and row content.
- Schemas must exist in each backend application database.
- Roles and privileges must be comparably configured on each backend server to ensure that the result set of SQL statements are identical on all servers.

If you use `password` authentication, the same password must be assigned to an associated user name on each database server. The same user `name/password` pair is used to connect pgPool-II to each backend connection.

Within a replication scenario, each backend is uniquely identified by the host name (or IP address) and port number on which the database server instance is listening for connections. You must ensure that the `pool_hba.conf` and `pg_hba.conf` files allow a connection between that server and the host on which pgPool-II will be running.

The following example demonstrates how to implement pgPool-II load balancing with two servers (the primary and replica nodes) in a Streaming Replication scenario. Configuring pgPool-II load balancing for a Slony replication scenario is similar; please consult the Slony documentation for information about configuring Slony replication.

### Step 1 - Configuring the Primary Node of the Replication Scenario

Open an SSH session with the primary node of the replication scenario, and modify the `pg_hba.conf` file (located in the `/opt/edb/as9.6/data` directory), adding connection information for the replication user (in the example that follows, `edbrepuser` resides on a standby node with an IP address of `107.178.217.178`):



```
host replication edbrepuser 107.178.217.178/32 md5
```

The connection information should specify the address of the standby node of the replication scenario, and your preferred authentication method.

Modify the `postgresql.conf` file (located in `/opt/edb/as9.6/data`), adding the following replication parameter and values to the end of the file:

```
wal_level = hot_standby
max_wal_senders = 3
checkpoint_segments = 8
wal_keep_segments = 8
```

Save the configuration file, and issue the following command in the OS Terminal window to restart the server:

```
/etc/init.d/edb-as-9.6 restart
```

Use the `sudo su -` command to assume the identity of the `enterprisedb` database superuser:

```
sudo su - enterprisedb
```

Then, start a `psql` session, connecting to the `edb` database:

```
psql -d edb
```

At the `psql` command line, create a user with the replication attribute:

```
CREATE ROLE edbrepuser WITH REPLICATION LOGIN PASSWORD
'password';
```

## Step 2 - Configuring the Standby Node of the Replication Scenario

Open an SSH session with the Standby server, and assume the identity of the database superuser (`enterprisedb`):

```
sudo su - enterprisedb
```

With your choice of editor, create a `.pgpass` file in the home directory of the `enterprisedb` user. The `.pgpass` file holds the password of the replication user in plain-text form; if you are using a `.pgpass` file, you should ensure that only trusted users have access to the `.pgpass` file:

Add an entry that specifies connection information for the replication user:

```
*:5444:*:edbrepuser:password
```

The server will enforce restrictive permissions on the `.pgpass` file; use the following command to set the file permissions:

```
chmod 600 .pgpass
```

Relinquish the identity of the database superuser:

```
exit
```

Then, assume superuser privileges:

```
sudo su -
```

Use your platform-specific command to stop the database server before replacing the `data` directory on the Standby node with the `data` directory of the Primary node. For information about controlling the service, see Section 5.

Then, delete the `data` directory on the Standby node:

```
rm -rf /opt/edb/as9.6/data
```

After deleting the existing `data` directory, use the `pg_basebackup` utility to copy the `data` directory of the Primary node to the Standby:

```
pg_basebackup --pgdata=/opt/edb/as9.6/data
--format=p --label=standby --host=146.148.46.44
--username=edbrepuser --password --xlog-method=stream
```

The call to `pg_basebackup` specifies the IP address of the Primary node and the name of the replication user created on the Primary node.

For more information about the options available with the `pg_basebackup` utility, see the PostgreSQL Core Documentation at:

<https://www.postgresql.org/docs/9.6/static/app-pgbasebackup.html>

When prompted by `pg_basebackup`, provide the password associated with the replication user.

After copying the `data` directory, change ownership of the directory to the database superuser (`enterprisedb`):

```
chown -R enterprisedb /opt/edb/as9.6/data
```

Navigate into the `data` directory:

```
cd /opt/edb/as9.6/data
```

With your choice of editor, create a file named `recovery.conf` (in the `/opt/edb/as9.6/data` directory) that includes:

```
standby_mode = on
trigger_file = /tmp/trigger_file
primary_conninfo = 'host=146.148.46.44 port=5444
                    user=edbrepuser password=password'
```

Please note that the `primary_conninfo` parameter specifies connection information for the replication user on the primary node of the replication scenario (in our example, `edbrepuser` resides on `146.148.46.44`).

Change ownership of the `recovery.conf` file to `enterprisedb`:

```
chown enterprisedb:enterprisedb recovery.conf
```

Modify the `postgresql.conf` file (located in `/opt/edb/as9.6/data`), specifying the following values at the end of the file:

```
wal_level = hot_standby
hot_standby = on
```

The `data` file has been copied from the Primary node, and will contain the replication parameters specified previously.

Then, restart the server:

```
/etc/init.d/edb-as-9.6 start
```

At this point, the Primary node will be replicating data to the Standby node.

### Step 3 - Configuring pgPool-II Load Balancing

Use your choice of editor to modify the `pgpool.conf` file. Within the `pgpool.conf` file, modify the parameter settings to specify that load balancing is enabled:

```
load_balance_mode = true
```

Then, specify the connections settings for the primary database node in the parameter set that ends with a `0`. For example:

```
backend_hostname0 = '146.148.46.44'
backend_port0 = 5444
backend_weight0 = 1
backend_data_directory0 = '/opt/edb/as9.6/data'
```

Then, specify the connections settings for each node to which queries will be distributed. Increment the number that follows the parameter name for each node, and provide connection details:

```
backend_hostname1 = '107.178.217.178'
backend_port1 = 5444
backend_weight1 = 1
backend_data_directory1 = '/opt/edb/as9.6/data'
```

Use the `backend_weight` parameter to specify how queries will be distributed amongst the nodes. Specify a value of `1` to indicate that you wish (qualified) queries to be equally distributed across the nodes of the replication scenario.

#### Step 4 - Restart pgPool-II and begin using your application

For information about starting the pgPool-II service, see Section 5.

#### *Commonly Used pgPool-II Parameters*

The following table lists `pgpool.conf` parameters that are used when implementing connection pooling:

Parameter Name	Description
<code>pool_conn_dbname</code>	Database name to which pgPool-II will connect. By default, pgPool-II will connect with <code>postgres</code> .
<code>listen_addresses</code>	Host name or IP address used by pgPool-II to listen for connections. Default is <code>localhost</code> . Change to <code>*</code> for all addresses.
<code>port</code>	Port for pgPool-II connections. Default is <code>9999</code> .
<code>pcp_port</code>	Port for PCP connections. Default is <code>9898</code> .
<code>backend_hostname0</code>	Host name or IP address for backend <code>0</code> . You can specify <code>''</code> if the backend and pgPool-II are running on the same host.
<code>backend_port0</code>	Port number for backend <code>0</code> .
<code>backend_weight0</code>	Weight for backend <code>0</code> (only in load balancing mode). Specify <code>1</code> for each backend if you want the load equally balanced, or decimal values ( <code>.9</code> , <code>.1</code> , etc.) to weight the load towards certain backends.
<code>backend_data_directory0</code>	Data directory for backend <code>0</code> .
<code>enable_pool_hba</code>	Set to <code>on</code> to use <code>pool_hba.conf</code> for client authentication.
<code>num_init_children</code>	Number of pools. Default is <code>32</code> .
<code>max_pool</code>	Number of connections per pool. Default is <code>4</code> .
<code>connection_cache</code>	Set to <code>on</code> to enable connection pooling.

The following table lists `pgpool.conf` parameters that are used when implementing replication and load balancing:

Parameter Name	Description
<code>allow_sql_comments</code>	If on, ignore SQL comments; modifications to this parameter require a reload of the <code>pgpool.conf</code> file.
<code>load_balance_mode</code>	Set to <code>on</code> to activate load balancing mode. If <code>load_balance_mode</code> is <code>on</code> and <code>replicate_select</code> is <code>off</code> ,

	<code>SELECT</code> statements are sent to one backend. The proportion of <code>SELECT</code> statements each backend receives is determined by parameter <code>backend_weight&lt;N&gt;</code> .
<code>ignore_leading_white_space</code>	Ignore leading white spaces of each query. Certain APIs such as <code>DBI/DBD:Pg</code> for Perl add white space that the user cannot control. Default is <code>on</code> .

### ***pgPool-II Client Authentication Configuration***

When pgPool-II is enabled, client applications connect to pgPool-II, which acts as a middleman for a Postgres server. A connecting client application is first authenticated with the pgPool-II server, and then authenticated with the Postgres server.

pgPool-II authentication properties are determined by parameter settings in the `pool_hba.conf` configuration file. The `pool_hba.conf` file is similar in format and function to the Postgres `pg_hba.conf` configuration file. Please consult the pgPool-II documentation for detailed information about `pool_hba.conf` entries.

To enable pgPool-II authentication:

- Copy file `pool_hba.conf.sample` to `pool_hba.conf`.

Modify the `pool_hba.conf` file, specifying authentication information for servers or users that you wish to allow to connect. Entries follow the same format used in the `pg_hba.conf` file.

Modify the `pgpool.conf` file, setting the `enable_pool_hba` parameter to `on`.

Restart pgPool-II to reload the pgPool-II configuration files.

Note: user names and passwords specified in the `pool_hba.conf` file will be used for authentication with the database server; you must also specify those user names and passwords in the database server's `pg_hba.conf` file.

### ***Connecting a Client to pgPool-II***

Client applications should connect directly to the pgPool-II listener port on the pgPool-II host. For example, to connect to the `edb` database using pgPool-II functionality, enter:

```
psql -d edb -U enterprisedb -h localhost -p 9999
```

When invoked at the `psql` prompt, the following `SHOW` command keywords will display pgPool-II information:

Command	Information Provided
SHOW pool_status	Displays pgPool-II configuration parameters and their name, value, and description.
SHOW pool_nodes	Displays a list of all configured nodes.
SHOW pool_processes	Displays a list of all pgPool-II processes waiting for connections or dealing with a connection.
SHOW pool_pools	Displays a list of pools.
SHOW pool_version	Displays the pgPool-II release number.

### ***PCP Configuration***

PCP is an administrative interface for pgPool-II that allows you to retrieve information about database nodes, pgPool-II child processes, etc. You should issue PCP commands from the Linux command line.

Before using PCP commands, you must modify the `pcp.conf` file, providing user names and passwords that you supply whenever you issue a PCP command. The user names in the `pcp.conf` file are completely independent of the database server user names and passwords.

Use the following steps to enable PCP:

- Copy the `pcp.conf.sample` file to `pcp.conf`.

Add an entry to the `pcp.conf` file of the following form:

```
username:md5_password
```

where:

`username` is a PCP user name.

`md5_password` is the PCP password in md5 format

You can use the `pg_md5` program to generate the encrypted password from the clear-text form as shown below:

```
$ pg_md5 mypassword
34819d7beeabb9260a5c854bc85b3e44
```

For example, the entry in the `pcp.conf` file for a PCP user named `pcpuser` with the password of `mypassword` is:

```
# USERID:MD5PASSWD
pcpuser:34819d7beeabb9260a5c854bc85b3e44
```

Restart the pgPool-II service. For information about restarting the pgPool-II service, see Section 5.

When issuing a PCP command, specify the PCP user name and the unencrypted form of the password:

```
$ pcp_node_info 5 localhost 9898 pcuser mypassword 0
localhost 5432 1 1.000000
```

After configuring PCP, you can use PCP commands to control pgPool-II and retrieve information. Specify the following arguments when calling PCP commands:

Argument	Description
timeout	Timeout value in seconds. PCP will disconnect if pgPool-II does not respond within the specified number of seconds.
host	The name of the pgPool-II host.
port	The PCP port number; the default value is 9898.
username	The PCP user name (as specified in <code>pcp.conf</code> .)
password	The password associated with the user name (as specified in <code>pcp.conf</code> ).

PCP recognizes the following commands:

PCP Command	Description
<code>pcp_node_count</code> <code>timeout host port</code> <code>username password</code>	Total number of nodes defined in <code>pgpool.conf</code>
<code>pcp_node_info timeout</code> <code>host port username</code> <code>password nodeid</code>	Displays information on the node given by <code>&lt;nodeid&gt;</code>
<code>pcp_proc_count</code> <code>timeout host port</code> <code>username password</code>	Displays the pgPool-II child process IDs
<code>pcp_proc_info timeout</code> <code>host port username</code> <code>password processid</code>	Displays information on the pgPool-II child process given by <code>&lt;processid&gt;</code>
<code>pcp_detach_node [-g]</code> <code>timeout host port</code> <code>username password</code> <code>nodeid</code>	Detaches the node specified by <code>&lt;nodeid&gt;</code> from pgPool-II. If <code>-g</code> is given, wait until all clients are disconnected (unless <code>client_idle_limit_in_recovery</code> is <code>-1</code> or <code>recovery_timeout</code> is expired).
<code>pcp_attach_node</code> <code>timeout host port</code> <code>username password</code> <code>nodeid</code>	Attaches the node specified by <code>&lt;nodeid&gt;</code> to pgPool-II.

## 7.8 *pgsnmpd*

*pgsnmpd* is an SNMP agent that can return hierarchical information about the current state of Advanced Server on a Linux system. *pgsnmpd* is distributed with and installed by the Advanced Server installer as part of the Database Server component. The *pgsnmpd* agent can operate as a stand-alone SNMP agent, as a pass-through sub-agent, or as an AgentX sub-agent.

After installing Advanced Server, you will need to update the `LD_LIBRARY_PATH` variable. Use the command:

```
$ export LD_LIBRARY_PATH=/opt/edb/as9.6/lib:$LD_LIBRARY_PATH
```

This command does not persistently alter the value of `LD_LIBRARY_PATH`; consult the documentation for your distribution of Linux for information about persistently setting the value of `LD_LIBRARY_PATH`.

The examples that follow demonstrate the simplest usage of *pgsnmpd*, implementing read only access. *pgsnmpd* is based on the `net-snmp` library; for more information about `net-snmp`, please visit:

<http://net-snmp.sourceforge.net>

### *Configuring pgsnmpd*

The *pgsnmpd* configuration file is named `snmpd.conf`. For information about the directives that you can specify in the configuration file, please review the `snmpd.conf` man page (`man snmpd.conf`).

You can create the configuration file by hand, or you can use the `snmpconf` perl script to create the configuration file. The perl script is distributed with `net-snmp` package. `net-snmp` is an open-source package available from:

<http://www.net-snmp.org>

To use the `snmpconf` configuration file wizard, download and install `net-snmp`. When the installation completes, open a command line and enter:

When the configuration file wizard opens, it may prompt you to read in an existing configuration file. Enter `none` to generate a new configuration file (not based on a previously existing configuration file).

`snmpconf` is a menu-driven wizard. Select menu item `1 : snmpd.conf` to start the configuration wizard. As you select each top-level menu option displayed by `snmpconf`, the wizard walks through a series of questions, prompting you for information required to build the configuration file. When you have provided information in each of the category



relevant to your system, enter `Finished` to generate a configuration file named `snmpd.conf`. Copy the file to:

```
/opt/edb/as9.6/share/
```

### ***Setting the Listener address***

By default, `pgsnmpd` listens on port 161. If the listener port is already being used by another service, you may receive the following error:

```
Error opening specified endpoint "udp:161".
```

You can specify an alternate listener port by adding the following line to your `snmpd.conf` file:

```
agentaddress $host_address:2000
```

The example instructs `pgsnmpd` to listen on UDP port 2000, where `$host_address` is the IP address of the server (e.g. `127.0.0.1`).

### ***Invoking pgsnmpd***

Ensure that an instance of Advanced Server is up and running (`pgsnmpd` will connect to this server). Open a command line and assume super-user privileges, before invoking `pgsnmpd` with a command that takes the following form:

```
path_to_EDBAS/bin/pgsnmpd -b -c path_to_EDBAS/share/snmpd.conf -C
"user=enterprisedb dbname=edb password=safe_password port=5444"
```

Where `path_to_EDBAS` specifies the Advanced Server installation directory.

Include the `-b` option to specify that `pgsnmpd` should run in the background.

Include the `-c` option, specifying the path and name of the `pgsnmpd` configuration file.

Include connection information for your installation of Advanced Server (in the form of a libpq connection string) after the `-C` option.

### ***Viewing pgsnmpd Help***

Include the `--help` option when invoking the `pgsnmpd` utility to view other `pgsnmpd` command line options:

```
pgsnmpd --help
Version PGSQL-SNMP-Ver1.0
```

```
usage: pgsnmpd [-s] [-b] [-c FILE ] [-x address ] [-g] [-C "Connect
String"]
-s : run as AgentX sub-agent of an existing snmpd process
-b : run in the background
-c : configuration file name
-g : use syslog
-C : libpq connection string
-x : address:port of a network interface
-V : display version strings
```

### ***Requesting information from pgsnmpd***

You can use `net-snmp` commands to query the `pgsnmpd` service. For example:

```
snmpgetnext -v 2c -c public localhost
.1.3.6.1.4.1.5432.1.4.2.1.1.0
```

In the above example:

`-v 2c` option instructs the `snmpgetnext` client to send the request in SNMP version 2c format.

`-c public` specifies the community name.

`localhost` indicates the host machine running the `pgsnmpd` server.

`.1.3.6.1.4.1.5432.1.4.2.1.1.0` is the identity of the requested object. To see a list of all databases, increment the last digit by one (e.g. `.1.1`, `.1.2`, `.1.3` etc.).

The encodings required to query any given object are defined in the MIB (Management Information Base). An SNMP client can monitor a variety of servers; the server type determines the information exposed by a given server. Each SNMP server describes the exposed data in the form of a MIB (Management information base). By default, `pgsnmpd` searches for MIB's in the following locations:

```
/usr/share/snmp/mibs
```

```
$HOME/.snmp/mibs
```

## 7.9 PL/Java

The PL/Java package provides access to Java stored procedures, triggers and functions via the JDBC interface. Unless otherwise noted, the commands and paths noted in the following section assume that you have performed an installation with the interactive installer.

Before installing PL/Java for use with a standard Java virtual machine (JVM) on a Linux system, you must first confirm that a Java runtime environment (version 1.5 or later) is installed on your system. Installation of a Java development kit also provides a Java runtime environment.

### 7.9.1 Installing PL/Java on Linux

The following steps outline the process of installing PL/Java on a Linux system:

- Edit the `postgresql.conf` file, located under the `data` directory of your Advanced Server installation, and add (or modify) the following settings:

```
pljava.classpath = 'path_to_pljava.jar'
pljava.libjvm_location = 'path_to_libjvm.so'
```

Where `path_to_pljava.jar` specifies the location of the `pljava.jar` file and `path_to_libjvm.so` specifies the location of the `libjvm.so` file.

For example, the following lists the paths for a default installation with Java version 1.8:

```
pljava.classpath = '/opt/edb/as9.6/share/pljava/pljava-1.5.0.jar'
pljava.libjvm_location = '/usr/lib/jvm/java-1.8.0-openjdk-1.8.0.91-1.b14.el6.x86_64/jre/lib/amd64/server/libjvm.so'
```


- Restart the database server.
- You can use the `CREATE EXTENSION` command to install PL/Java. To install the PL/Java extension, login to the database in which you want to install PL/Java with the `psql` or `pgAdmin` client, and invoke the following command:

```
CREATE EXTENSION pljava;
```

- To confirm that PL/Java is installed, invoke the following command:

```
select * from pg_language where lanname like 'java%';
```

The `edb-psql` client displays two rows indicating that `java` and `javau` (Java Untrusted) have been installed in the database (see Figure 7.2):



```
Terminal
File Edit View Search Terminal Help
edb=# select * from pg_language where lanname like 'java%';
 lanname | lanowner | lanispl | lanpltrusted | lanplcallfoid | laninline | lanvalidat
or |          |         |              |               |          |
-----+-----+-----+-----+-----+-----+-----
 java   |      10 | t       | t           |      16658 |      0 |
0 | {enterprisedb=U/enterprisedb}
 javau  |      10 | t       | f           |      16659 |      0 |
0 |
(2 rows)

edb=#
```

*Figure 7.2 -Confirming PL/Java installation.*

## 7.9.2 Installing PL/Java on Windows

The following steps outline the process of installing PL/Java on a Windows system:

- Edit the `postgresql.conf` file and add (or modify) the following settings:

```
pljava.classpath = 'path_to_EDBAS\lib\pljava.jar'
pljava.libjvm_location = 'path_to_libjvm.so'
```

Where `path_to_EDBAS` specifies the location of the Advanced Server installation. For example, the following is the configuration setting for a default installation:

```
pljava.classpath = 'C:\Program
Files\edb\as9.6\lib\pljava.jar'
```

- Restart the database server.
- Modify the `PATH` setting used by the server, adding the following two entries:

```
%JRE_HOME%\bin;%JRE_HOME%\bin\client
```

Where `JRE_HOME` specifies the installation directory of your Java runtime environment. If you have a Java development kit, substitute the location of `$JDK_HOME/jre` for `JRE_HOME`.

- Use the Postgres `CREATE EXTENSION` command to install PL/Java. To run the installation script, use the `psql` or `pgAdmin` client to connect to the database in which you wish to install PL/Java and invoke the following command:

```
CREATE EXTENSION pljava
```

- To confirm that PL/Java is installed, invoke the following command:

```
select * from pg_language where lanname like 'java%';
```

The client will return a result set that includes `java` and `javau` (Java Untrusted).

### 7.9.3 Using PL/Java

To create a PL/Java program, you must first create a Java class that contains at least one static method, and then you must compile that class into a `.class` or `.jar` file. Next, you declare the Java function within SQL using the `CREATE FUNCTION` command. The `CREATE FUNCTION` command gives a SQL name to the function and associates the compiled class (and method name) with that function name.

For example, the following `CREATE FUNCTION` statement creates a function names `getsysprop`:

```
CREATE FUNCTION getsysprop(VARCHAR)
RETURNS VARCHAR
AS 'java.lang.System.getProperty'
LANGUAGE java;
SELECT getsysprop('user.home');
```

When invoked, `getsysprop` will execute the `getProperty` (static) method defined within the `java.lang.System` class.

#### Creating and Installing a PL/Java Program

The example that follows demonstrates the procedures used to create and install a simple `HelloWorld` program:

- Save the following code sample to a file named `HelloWorld.java`

```
package com.mycompany.helloworld;
public class HelloWorld
{
    public static String helloWorld()
    {
        return "Hello World";
    }
}
```

- Compile the file:

```
$ javac HelloWorld.java
```

and save it in a folder hierarchy as:

```
com/mycompany/helloworld/HelloWorld.class
```

- Create an archive file (a JAR file) named `helloworld.jar`:

```
$ jar cf helloworld.jar \
com/mycompany/helloworld/HelloWorld.class
```

- Open the `edb-psql` client, and install the jar file with the following command:

```
edb=# SELECT
sqlj.install_jar('file:///<file_path>/helloworld.jar',
'helloworld', true);
```

To confirm that the jar file has been loaded correctly, perform a `SELECT` statement on the `sqlj.jar_entry` and `sqlj.jar_repository` tables.

- Set the classpath as:

```
edb=# SELECT sqlj.set_classpath('public',
'helloworld');
```

The `sqlj.classpath_entry` table will now include an entry for the `helloworld` class file.

- Create a function that uses Java to call the static function declared in the jar file:

```
CREATE OR REPLACE FUNCTION helloworld()
  RETURNS "varchar" AS
  'com.mycompany.helloworld.HelloWorld.helloWorld'
  LANGUAGE 'java' VOLATILE;
```

- Execute the function:

```
edb=# SELECT * FROM helloworld();
```

You should see the output:

```
helloworld
-----
Hello World
(1 row)
```

The official PL/Java distribution is distributed with examples and documentation. For more information about using PL/Java, please see the project page at:

<https://github.com/tada/pljava/wiki>

## 7.10 PL/Perl

The PL/Perl procedural language allows Advanced Server users to use Perl functions in Advanced Server applications. Before using PL/Perl, you must use the Language Pack installer (available via StackBuilder Plus) to install Perl. For information about using StackBuilder Plus, see Section 4.5. After downloading and installing the Language Pack, perform the OS specific Language Pack configuration steps outlined in Section 7.3.

You must install PL/Perl in each database (or in a template database) before creating a PL/Perl function. Use the `CREATE LANGUAGE` command at the EDB-PSQL command line to install PL/Perl. Open the EDB-PSQL client, establish a connection to the database in which you wish to install PL/Perl, and enter the command:

```
CREATE LANGUAGE plperl;
```

Advanced Server confirms that the language is loaded with the response:

```
CREATE LANGUAGE;
```

You can now use the features of the PL/Perl language from within Advanced Server. The following PL/Perl example creates a function named `perl_max` that returns the larger of two integer values:

```
CREATE OR REPLACE FUNCTION perl_max (integer, integer) RETURNS integer AS
$$
    if ($_[0] > $_[1])
    { return $_[0]; }
    return $_[1];
$$ LANGUAGE plperl;
```

Pass two values when calling the function:

```
SELECT perl_max(1, 2);
```

Advanced Server returns:

```
perl_max
-----
         2
(1 row)
```

For more information about using the Perl procedural language with Advanced Server, consult the official Postgres documentation available from EnterpriseDB at:

<https://www.postgresql.org/docs/9.6/static/plperl.html>



## 7.11 PL/Python

The PL/Python procedural language allows Advanced Server users to create (and execute) functions written in Python within Advanced Server applications. The version of PL/Python used by Advanced Server is untrusted (`plpython3u`); it offers no restrictions on users to prevent potential security risks.

Please note that Advanced Server includes a major change in the Python installation for Linux systems. In previous releases, `plpython` was statically linked with ActiveState's python library. The EnterpriseDB Language Pack installer dynamically links with our shared object for python. In ActiveState Linux installers for Python, there was no dynamic library. As a result of these changes, `plpython` will no longer work with ActiveState installers.

You can use StackBuilder Plus to invoke the Language Pack installer. For information about using StackBuilder Plus, see Section [4.5](#). After downloading and installing the Language Pack, perform the OS specific configuration steps outlined in Section [7.3](#).

Install PL/Python in each database (or in a template database) before creating a PL/Python function. You can use the `CREATE LANGUAGE` command at the EDB-PSQL command line to install PL/Python. Use EDB-PSQL to connect to the database in which you wish to install PL/Python, and enter the command:

```
CREATE LANGUAGE plpython3u;
```

Advanced Server confirms that the language is loaded with the response:

```
CREATE LANGUAGE
```

After installing PL/Python in your database, you can use the features of the PL/Python language from within Advanced Server.

Please note: The indentation shown in the following example must be included as you enter the sample function in EDB-PSQL. The following PL/Python example creates a function named `pymax` that returns the larger of two integer values:

```
CREATE OR REPLACE FUNCTION pymax (a integer, b integer) RETURNS integer
AS
$$
    if a > b:
        return a
    return b
$$ LANGUAGE plpython3u;
```

When calling the `pymax` function, pass two values as shown below:

```
SELECT pymax(12, 3);
```

Advanced Server returns:

```
pymax
-----
      12
(1 row)
```

For more information about using the Python procedural language with Advanced Server, consult the official PostgreSQL documentation available from EnterpriseDB at:

<https://www.postgresql.org/docs/9.6/static/plpython.html>

## 7.12 PL/Tcl

The PL/Tcl procedural language allows Advanced Server users to use Tcl/Tk functions in Advanced Server applications. Before using PL/Tcl with Advanced Server you must install TCL. You can use StackBuilder Plus to invoke the Language Pack installer (for information about using StackBuilder Plus, see Section 4.5). After downloading and installing the Language Pack, perform the operating system specific configuration steps outlined in Section 7.3.

PL/Tcl is distributed with EDB Postgres Advanced Server. You must install PL/Tcl in each database (or in a template database) before creating a PL/Tcl function. Use the `CREATE LANGUAGE` command at the EDB-PSQL command line to install PL/Tcl. Use the `psql` client to connect to the database in which you wish to install PL/Tcl, and enter the command:

```
CREATE LANGUAGE pltcl;
```

After creating the `pltcl` language, you can use the features of the PL/Tcl language from within Advanced Server. The following PL/Tcl example creates a function named `tcl_max` that returns the larger of two integer values:

```
CREATE OR REPLACE FUNCTION tcl_max(integer, integer) RETURNS integer AS
$$
    if {[argisnull 1]} {
        if {[argisnull 2]} { return_null }
        return $2
    }
    if {[argisnull 2]} { return $1 }
    if {$1 > $2} {return $1}
    return $2
$$ LANGUAGE pltcl;
```

Pass two values when calling the function:

```
SELECT tcl_max(1, 2);
```

Advanced Server returns:

```
tcl_max
-----
      2
(1 row)
```

For more information about using the Tcl procedural language with Advanced Server, consult the official Postgres documentation available from EnterpriseDB at:

<https://www.postgresql.org/docs/9.6/static/pltcl.html>

## 7.13 PostGIS

PostGIS is a PostgreSQL extension that allows you to store Geographic Information Systems (GIS) objects in an Advanced Server database. PostGIS includes functions for analyzing and processing GIS objects, and support for GiST-based R-Tree spatial indexes.

### Installing PostGIS with a Package Manager

You can use EnterpriseDB packages to add PostGIS to your Advanced Server installation. Before using a package to install PostGIS, you must install the EPEL repository. For information about installing the EPEL repository, see Section [4.7](#).

Then, invoke the PostGIS meta installer package with the command:

```
yum install edb-as96-postgis
```

The `edb-as96-postgis` package installs the following supporting Advanced Server component packages:

```
edb-as96-postgis-2.3
edb-as96-postgis-utils
edb-as96-postgis-docs
edb-as96-postgis-core
```

Additional support for PostGIS is also provided by the following packages:

Package	Provides
<code>cfitsio</code>	Library for manipulating FITS data files
<code>gdal</code>	GIS file format library
<code>geos</code>	A C++ port of the Java Topology Suite
<code>hdf5</code>	General purpose library and file format for scientific data
<code>libdap</code>	The C++ DAP2 library
<code>libgeotiff</code>	GeoTIFF format library
<code>librx</code>	POSIX regex functions
<code>netcdf</code>	Libraries for the Unidata network Common Data Form
<code>ogdi</code>	Open Geographic Datastore Interface
<code>proj</code>	Cartographic projection software (PROJ.4)

If you are installing PostGIS with a package manager, please note that you must manually create the `template_postgis` database and any PostGIS extensions required. For complete information about managing your PostGIS installation, please visit the official project website at:

<http://postgis.net/documentation/>

### Using StackBuilder Plus to Install PostGIS

If you have used the graphical Setup wizard to install Advanced Server, you can use StackBuilder Plus to add PostGIS to your installation.

On Linux, navigate through the Applications menu to the EDB Postgres menu; open the Add-ons menu, and select StackBuilder Plus. If you are using Windows, select StackBuilder Plus from the Apps menu. Select your Advanced Server installation from the drop down listbox on the Welcome window and click Next to continue to the application selection page. Expand the Spatial Extensions node, and check the box next to PostGIS v2.1.x.x to download and install your selected version of PostGIS.

Click Next to continue; the StackBuilder Plus wizard will walk you through the installation process. During the installation, StackBuilder Plus will install PostGIS and create the `template_postgis` database, as well as the PostGIS functions.

### 7.13.1 Upgrading to PostGIS 2.3

If you are upgrading an existing Advanced Server installation (version 9.1 or prior) that contains PostGIS to a later version of Advanced Server, you must perform a manual upgrade. The `pg_upgrade` tool does not support upgrades of spatially enabled databases (a database that contains PostGIS database objects (functions, types, operators, tables, etc.).

To upgrade a database using PostGIS 1.x to PostGIS 2.x, use the `pg_dump` and `pg_restore` commands to perform a dump and restore of the PostGIS database. Please note: the host must contain an installation of Perl to perform this upgrade.

For complete information about PostGIS and performing an upgrade, see the PostGIS documentation at:

<http://postgis.refrains.net/documentation/manual-2.0>

The following summarizes the basic steps required to perform an upgrade to Advanced Server 9.6 when your current version of Advanced Server has PostGIS 1.x installed along with PostGIS databases:

- In your current Advanced Server cluster, use `pg_dump` to create a custom-format backup of each PostGIS 1.x database.
- Drop the PostGIS databases that were backed up, drop database template `template_postgis`, and uninstall PostGIS.
- Install Advanced Server 9.6, but do not install PostGIS at this time.
- Perform the upgrade to Advanced Server 9.6 using `pg_upgrade` as described in Section 8.3, *Upgrading to Advanced Server 9.6*. This upgrades all non-PostGIS databases to Advanced Server 9.6.
- Start up Advanced Server 9.6 and use StackBuilder Plus to install PostGIS 2.3.
- For each backup file created from a PostGIS 1.x database, create a new, empty PostGIS database and restore each backup file into a new PostGIS database using Perl script `postgis_restore.pl`.

The following example illustrates an upgrade from Advanced Server 9.1 to Advanced Server 9.6 when PostGIS 1.5 is installed in Advanced Server 9.1, and a PostGIS database named `roadmaps` exists in the Advanced Server 9.1 cluster.

The `roadmaps` PostGIS database was created in Advanced Server 9.1 using the following command given in EDB-PSQL:

```
CREATE DATABASE roadmaps TEMPLATE=template_postgis;
```

In the roadmaps database, table roads was created and loaded with some rows:

```
CREATE TABLE roads (id INTEGER, name VARCHAR2(128));

SELECT AddGeometryColumn('roads', 'geom', -1, 'GEOMETRY',
2);

INSERT INTO roads (id, geom, name) VALUES (1,
GeomFromText('LINESTRING(0 10,0 0)', -1), 'Beacon Road');
INSERT INTO roads (id, geom, name) VALUES (2,
GeomFromText('LINESTRING(0 0,0 10)', -1), 'Violet Road');
INSERT INTO roads (id, geom, name) VALUES (3,
GeomFromText('LINESTRING(0 0,10 0)', -1), 'Skelton
Street');
INSERT INTO roads (id, geom, name) VALUES (4,
GeomFromText('LINESTRING(0 0,10 10)', -1), 'Fifth Avenue');
INSERT INTO roads (id, geom, name) VALUES (5,
GeomFromText('LINESTRING(10 0,0 0)', -1), 'Lipton Street');

CREATE INDEX roads_index ON roads USING GIST(geom);
```

For purposes of this example, roadmaps is assumed to be the only PostGIS database in the cluster.

### Step 1 - Back up PostGIS databases

Following the directions for performing a hard upgrade, run `pg_dump` to create a backup file for the roadmaps database using the following command:

```
export PATH=$PATH:/opt/PostgresPlus/9.1AS/bin

pg_dump -U enterprisedb -Fc -b -v -f "/tmp/roadmaps.backup"
roadmaps
```

Please note: The backup file must be in custom-format as specified by the `-Fc` option. This is required by the Perl script you will later use to load the new PostGIS database.

### Step 2 - Drop the PostGIS database template

While connected to database `template1` as a superuser, drop the database template `template_postgis` as shown by the following:

```
template1=# UPDATE pg_database SET datistemplate = false
WHERE datname = 'template_postgis';
UPDATE 1
template1=# DROP DATABASE template_postgis;
DROP DATABASE
```

### Step 3 - Drop PostGIS databases

Before dropping a PostGIS database, be sure you have a backup (see Step 1). Then, drop the `roadmaps` database:

```
template1=# DROP DATABASE roadmaps;
DROP DATABASE
```

#### Step 4 - Uninstall PostGIS

To uninstall PostGIS, assume superuser privileges and invoke the following script (located in the Advanced Server home directory):

```
uninstall-postgis
```

#### Step 5 - Perform the upgrade to Advanced Server 9.6 using `pg_upgrade`

Perform steps 1 through 7 described in Section [8.3](#) to upgrade to Advanced Server 9.6.

Please note: At this time, skip step 8 of Section [8.3](#). Do not restore the authentication settings in the `pg_hba.conf` file; the server must use `trust` authentication when loading the new PostGIS databases from the backup files.

#### Step 6 - Start Advanced Server 9.6 and use StackBuilder Plus to download and install PostGIS

For information about using StackBuilder Plus, see Section [4.5](#), *Using StackBuilder Plus*.

#### Step 7 - Create a new PostGIS database

Create the PostGIS database with the template `template_postgis` as shown by the following:

```
createdb -U enterprisedb -T template_postgis -p 5445
roadmaps
```

#### Step 8 - Add legacy PostGIS objects if necessary

If your applications require legacy PostGIS functions, these can be added using the `legacy.sql` script:

```
edb-psql -d roadmaps -U enterprisedb -p 5445 -f
"/opt/edb/as9.6/share/contrib/postgis-2.0/legacy.sql"
```

These legacy functions can later be removed with the `uninstall_legacy.sql` script.

#### Step 9 - Restore the PostGIS database from the backup file



Run the Perl script `postgis_restore.pl` and pipe the output to EDB-PSQL to load the database from the backup file. This script contains functionality to skip objects known to PostGIS (since updated versions of these objects have been created in the new database you are loading) as well as convert certain old PostGIS constructs into new ones.

Be sure `trust` authentication mode is set in `pg_hba.conf` before running this script.

```
$ export PATH=$PATH:/opt/edb/as9.6/bin
$
$ perl /opt/edb/as9.6/share/contrib/postgis-2.0/postgis_restore.pl
"/tmp/roadmaps.backup" | edb-psql -U enterprisedb -p 5445 roadmaps 2>
/tmp/roadmaps_loaderr.txt
Converting /tmp/roadmaps.backup to ASCII on stdout...
  Reading list of functions to ignore...
  Writing manifest of things to read from dump file...
  Writing ASCII to stdout...
  WARNING: SRID -1 converted to 0 (official UNKNOWN)
ALTER TABLE
ALTER TABLE
SELECT 3911
DELETE 3911
SET
SET
SET
.
.
.
```

### Step 10 - Verify the PostGIS database has been properly restored

The following query verifies the content of the `roads` table in the `roadmaps` database:

```
$ edb-psql -d roadmaps -U enterprisedb -p 5445
edb-psql (9.6.0.0)
Type "help" for help.

roadmaps=# SELECT id, ST_AsText(geom) AS geom, name FROM roads ORDER BY id;
 id |          geom          | name
----+-----+-----
  1 | LINESTRING(0 10,0 0) | Beacon Road
  2 | LINESTRING(0 0,0 10) | Violet Road
  3 | LINESTRING(0 0,10 0) | Skelton Street
  4 | LINESTRING(0 0,10 10) | Fifth Avenue
  5 | LINESTRING(10 0,0 0) | Lipton Street
(5 rows)
```

### Step 11 - Repeat for each PostGIS database backup

Repeat steps 7 through 10 for each PostGIS database backup file created in Step 1.

### Step 12 - Restore the authentication settings in the `pg_hba.conf` file

Update the contents of the `pg_hba.conf` file to reflect your preferred authentication settings.

## 7.14 SQL Profiler

SQL Profiler helps locate and optimize poorly running SQL code. Before using SQL Profiler, you must:

### Step 1 - Install SQL Profiler

SQL Profiler is installed by the Advanced Server Installer, or you can download and install SQL Profiler into a managed database instance.

### Step 2 - Add the SQL Profiler library

Modify the `postgresql.conf` parameter file for the instance to include the SQL Profiler library in the `shared_preload_libraries` configuration parameter.

For Linux installations, the parameter value should include:

```
$libdir/sql-profiler
```

On Windows, the parameter value should include:

```
$libdir\sql-profiler.dll
```

### Step 3 - Create the functions used by SQL Profiler

The SQL Profiler installation program places a SQL script (named `sql-profiler.sql`) in:

On Linux:

```
/opt/edb/as9.6/share/contrib/
```

On Windows:

```
C:\Program Files\edb\as9.6\share\contrib\
```

Use the `psql` command line interface to run the `sql-profiler.sql` script in the database specified as the Maintenance Database on the server you wish to profile. If you are using Advanced Server, the default maintenance database is named `edb`. If you are using a PostgreSQL instance, the default maintenance database is named `postgres`.

The following command uses the `psql` command line to invoke the `sql-profiler.sql` script on a Linux system:

```
$ /opt/edb/as9.6/bin/psql -U user_name database_name <
/opt/edb/as9.6/share/contrib/sql-profiler.sql
```

**Step 4 - Stop and restart the server for the changes to take effect**

After configuring SQL Profiler, it is ready to use with all databases that reside on the server. You can take advantage of SQL Profiler functionality with EDB Postgres Enterprise Manager; for more information about Postgres Enterprise Manager, visit the EnterpriseDB website at:

<http://www.enterprisedb.com/products/postgres-enterprise-manager>

***Troubleshooting***

If (after performing an upgrade to a newer version of SQL Profiler) you encounter an error that contains the following text:

```
An error has occurred:  
ERROR: function return row and query-specified return row do not  
match.  
DETAIL: Returned row contains 11 attributes, but the query  
expects 10.
```

To correct this error, you must replace the existing query set with a new query set. First, uninstall SQL Profiler by invoking the `uninstall-sql-profiler.sql` script, and then reinstall SQL Profiler by invoking the `sql-profiler.sql` script.

## 7.15 *sslutils*

*sslutils* is a Postgres extension that provides SSL certificate generation functions to Advanced Server, for use by the EDB Postgres Enterprise Manager server. *sslutils* is installed by the Advanced Server RPM Meta Installer and the Advanced Server graphical installer.

### *sslutils Functions*

The *sslutils* package provides the functions described below.

`openssl_rsa_generate_key`

The `openssl_rsa_generate_key` function generates an RSA private key. The function signature is:

```
openssl_rsa_generate_key(integer) RETURNS text
```

When invoking the function, pass the number of bits as an integer value; the function returns the generated key.

`openssl_rsa_key_to_csr`

The `openssl_rsa_key_to_csr` function generates a certificate signing request (CSR). The signature is:

```
openssl_rsa_key_to_csr(text, text, text, text, text,  
text, text) RETURNS text
```

The text arguments expected by the `openssl_rsa_key_to_csr` function are:

Argument 1: The name of the RSA key file.

Argument 2: The common name (e.g., `agentN`) of the agent that will use the signing request.

Argument 3: The name of the country in which the server resides.

Argument 4: The name of the state in which the server resides.

Argument 5: The location (city) within the state in which the server resides.

Argument 6: The name of the organization unit requesting the certificate.

Argument 7: The email address of the user requesting the certificate.

The function generates and returns the certificate signing request.

```
openssl_csr_to_cert
```

The `openssl_csr_to_cert` function generates a self-signed certificate or a certificate authority certificate. The signature is:

```
openssl_csr_to_cert(text, text, text) RETURNS text
```

The text arguments expected by the `openssl_csr_to_cert` function are:

Argument 1: The name of the certificate signing the request.

Argument 2: The path to the certificate authority certificate, or `NULL` if generating a certificate authority certificate.

Argument 3: The path to the certificate authority's private key or (if argument 2 is `NULL`) the path to a private key.

The function returns the self-signed certificate or certificate authority certificate.

```
openssl_rsa_generate_crl
```

The `openssl_rsa_generate_crl` function generates a default certificate revocation list. The signature is:

```
openssl_rsa_generate_crl(text, text) RETURNS text
```

The text arguments expected by the `openssl_rsa_generate_crl` function are:

Argument 1: The path to the certificate authority certificate.

Argument 2: The path to the certificate authority private key.

The function returns the certificate revocation list.

## 8 Upgrading an Installation With `pg_upgrade`

While minor upgrades between versions are fairly simple, and require only the installation of new executables, past major version upgrades have been both expensive and time consuming. `pg_upgrade` facilitates migration between any version of Advanced Server (version 9.0 or later), and any subsequent release of Advanced Server that is supported on the same platform.

Without `pg_upgrade`, to migrate from an earlier version of Advanced Server to Advanced Server 9.6, you must export all of your data using `pg_dump`, install the new release, run `initdb` to create a new cluster, and then import your old data. If you have a significant amount of data, that can take a considerable amount of time and planning. You may also have to use additional storage to temporarily accommodate both the original data and the exported data.

*`pg_upgrade` can reduce both the amount of time required and the disk space required for many major-version upgrades.*

The `pg_upgrade` utility performs an in-place transfer of existing data between Advanced Server and any subsequent version.

Several factors determine if an in-place upgrade is practical:

- The on-disk representation of user-defined tables must not change between the original version and the upgraded version.
- The on-disk representation of data types must not change between the original version and the upgraded version.
- To upgrade between major versions of Advanced Server with `pg_upgrade`, both versions must share a common binary representation for each data type. Therefore, you cannot use `pg_upgrade` to migrate from a 32-bit to a 64-bit Linux platform.

Before performing a version upgrade, `pg_upgrade` will verify that the two clusters (the old cluster and the new cluster) are compatible.

If the upgrade involves a change in the on-disk representation of database objects or data, or involves a change in the binary representation of data types, `pg_upgrade` will be unable to perform the upgrade; to upgrade, you will have to `pg_dump` the old data and then import that data into the new cluster.

The `pg_upgrade` executable is distributed with Advanced Server 9.6, and is installed as part of the `Database Server` component; no additional installation or configuration steps are required.

## 8.1 Performing an Upgrade - Overview

To upgrade an earlier version of Advanced Server to the current version, you must:

- Install the current version of Advanced Server. The new installation must contain the same supporting server components as the old installation.
- Empty the target database or create a new target cluster with `initdb`.
- Place the `pg_hba.conf` file for both databases in `trust` authentication mode (to avoid authentication conflicts).
- Shut down the old and new Advanced Server services.
- Invoke the `pg_upgrade` utility.

When `pg_upgrade` starts, it performs a compatibility check to ensure that all required executables are present and contain the expected version numbers. The verification process also checks the old and new `$PGDATA` directories to ensure that the expected files and subdirectories are in place. If the verification process succeeds, `pg_upgrade` starts the old `postmaster` and runs `pg_dumpall --schema-only` to capture the metadata contained in the old cluster. The script produced by `pg_dumpall` is used in a later step to recreate all user-defined objects in the new cluster.

Note that the script produced by `pg_dumpall` recreates only user-defined objects and not system-defined objects. The new cluster will *already* contain the system-defined objects created by the latest version of Advanced Server.

After extracting the metadata from the old cluster, `pg_upgrade` performs the bookkeeping tasks required to sync the new cluster with the existing data.

`pg_upgrade` runs the `pg_dumpall` script against the new cluster to create (empty) database objects of the same shape and type as those found in the old cluster. Then, `pg_upgrade` links or copies each table and index from the old cluster to the new cluster.

### 8.1.1 Linking versus Copying

When invoking `pg_upgrade`, you can use a command-line option to specify whether `pg_upgrade` should *copy* or *link* each table and index in the old cluster to the new cluster.

Linking is much faster because `pg_upgrade` simply creates a second name (a hard link) for each file in the cluster; linking also requires no extra workspace because `pg_upgrade` does not make a copy of the original data. When linking the old cluster and the new cluster, the old and new clusters share the data; note that after starting the new cluster, your data can no longer be used with the previous version of Advanced Server.

If you choose to copy data from the old cluster to the new cluster, `pg_upgrade` will still reduce the amount of time required to perform an upgrade compared to the traditional `dump/restore` procedure. `pg_upgrade` uses a file-at-a-time mechanism to copy data files from the old cluster to the new cluster (versus the row-by-row mechanism used by `dump/restore`). When you use `pg_upgrade`, you avoid building indexes in the new cluster; each index is simply copied from the old cluster to the new cluster. Finally, using a `dump/restore` procedure to upgrade requires a great deal of workspace to hold the intermediate text-based dump of all of your data, while `pg_upgrade` requires very little extra workspace.

Data that is stored in user-defined tablespaces is not copied to the new cluster; it stays in the same location in the file system, but is copied into a subdirectory whose name reflects the version number of the new cluster. To manually relocate files that are stored in a tablespace after upgrading, move the files to the new location and update the symbolic links (located in the `pg_tblspc` directory under your cluster's `data` directory) to point to the files.



## 8.2 Invoking `pg_upgrade`

When invoking `pg_upgrade`, you must specify the location of the old and new cluster's PGDATA and executable (`/bin`) directories, as well as the name of the Advanced Server superuser, and the ports on which the installations are listening. A typical call to invoke `pg_upgrade` to migrate from Advanced Server 9.5 to Advanced Server 9.6 takes the form:

```
pg_upgrade --old-datadir path_to_9.5_data_directory --new-
datadir path_to_9.6_data_directory --user superuser_name --
old-bindir path_to_9.5_bin_directory --new-bindir
path_to_9.6_bin_directory --old-port 9.5_port --new-port
9.6_port
```

Where:

```
--old-datadir path_to_9.5_data_directory
```

Use the `--old-datadir` option to specify the complete path to the data directory within the Advanced Server 9.5 installation.

```
--new-datadir path_to_9.6_data_directory
```

Use the `--new-datadir` option to specify the complete path to the data directory within the Advanced Server 9.6 installation.

```
--username superuser_name
```

Include the `--username` option to specify the name of the Advanced Server superuser. The superuser name should be the same in both versions of Advanced Server. By default, when Advanced Server is installed in Oracle mode, the superuser is named `enterprisedb`. If installed in PostgreSQL mode, the superuser is named `postgres`.

If the Advanced Server superuser name is not the same in both clusters, the clusters will not pass the `pg_upgrade` consistency check.

```
--old-bindir path_to_9.5_bin_directory
```

Use the `--old-bindir` option to specify the complete path to the `bin` directory in the Advanced Server 9.5 installation.

```
--new-bindir path_to_9.6_bin_directory
```

Use the `--new-bindir` option to specify the complete path to the `bin` directory in the Advanced Server 9.6 installation.

```
--old-port 9.5_port
```

Include the `--old-port` option to specify the port on which Advanced Server 9.5 listens for connections.

```
--new-port 9.6_port
```

Include the `--new-port` option to specify the port on which Advanced Server 9.6 listens for connections.

## 8.2.1 Command Line Options - Reference

`pg_upgrade` accepts the following command line options; each option is available in a long form or a short form:

```
-b path_to_old_bin_directory
--old-bindir path_to_old_bin_directory
```

Use the `-b` or `--old-bindir` keyword to specify the location of the old cluster's executable directory.

```
-B path_to_new_bin_directory
--new-bindir path_to_new_bin_directory
```

Use the `-B` or `--new-bindir` keyword to specify the location of the new cluster's executable directory.

```
-c
--check
```

Include the `-c` or `--check` keyword to specify that `pg_upgrade` should perform a consistency check on the old and new cluster without performing a version upgrade.

```
-d path_to_old_data_directory
--old-datadir path_to_old_data_directory
```

Use the `-d` or `--old-datadir` keyword to specify the location of the old cluster's data directory.

```
-D path_to_new_data_directory
--new-datadir path_to_new_data_directory
```

Use the `-D` or `--new-datadir` keyword to specify the location of the new cluster's data directory.

Please note: Data that is stored in user-defined tablespaces is not copied to the new cluster; it stays in the same location in the file system, but is copied into a subdirectory whose name reflects the version number of the new cluster. To manually relocate files that are stored in a tablespace after upgrading, you must move the files to the new location and update the symbolic links (located in the `pg_tblspc` directory under your cluster's data directory) to point to the files.

```
-j
--jobs
```

Include the `-j` or `--jobs` keyword to specify the number of simultaneous processes or threads to use during the upgrade.

```
-k
--link
```

Include the `-k` or `--link` keyword to create a hard link from the new cluster to the old cluster. See Section [8.1.1, \*Linking versus Copying\*](#) for more information about using a symbolic link.

```
-o options
--old-options options
```

Use the `-o` or `--old-options` keyword to specify options that will be passed to the old `postgres` command. Enclose options in single or double quotes to ensure that they are passed as a group.

```
-O options
--new-options options
```

Use the `-O` or `--new-options` keyword to specify options to be passed to the new `postgres` command. Enclose options in single or double quotes to ensure that they are passed as a group.

```
-p old_port_number
--old-port old_port_number
```

Include the `-p` or `--old-port` keyword to specify the port number of the Advanced Server installation that you are upgrading.

```
-P new_port_number
--new-port new_port_number
```

Include the `-P` or `--new-port` keyword to specify the port number of the new Advanced Server installation.

Please note: If the original Advanced Server installation is using port number 5444 when you invoke the Advanced Server 9.6 installer, the installer will recommend using listener port 5445 for the new installation of Advanced Server.

```
-r
--retain
```

During the upgrade process, `pg_upgrade` creates four append-only log files; when the upgrade is completed, `pg_upgrade` deletes these files. Include the `-r` or `--retain` option to specify that the server should retain the `pg_upgrade` log files.

```
-U user_name  
--username user_name
```

Include the `-U` or `--username` keyword to specify the name of the Advanced Server database superuser. The same superuser must exist in both clusters.

```
-v  
--verbose
```

Include the `-v` or `--verbose` keyword to enable verbose output during the upgrade process.

```
-V  
--version
```

Use the `-V` or `--version` keyword to display version information for `pg_upgrade`.

```
-?  
-h  
--help
```

Use `-?`, `-h` or `--help` options to display `pg_upgrade` help information.

### 8.3 Upgrading to Advanced Server 9.6 – Step-by-Step

You can use `pg_upgrade` to upgrade from an existing installation of Advanced Server into the cluster built by the Advanced Server 9.6 installer or into an alternate cluster created using the `initdb` command. In this section, we will provide the details of upgrading into the cluster provided by the installer.

The basic steps to perform an upgrade into an empty cluster created with the `initdb` command are the same as the steps to upgrade into the cluster created by the Advanced Server 9.6 installer, but you can omit Step 2 (*Empty the `edb` database*), and substitute the location of the alternate cluster when specifying a target cluster for the upgrade.

If a problem occurs during the upgrade process, you can revert to the previous version. See Section [8.5](#), *Reverting to the Old Cluster* for detailed information about this process.

You must be an operating system superuser or Windows Administrator to perform an Advanced Server upgrade.

#### Step 1 - Install the New Server

Install Advanced Server 9.6, specifying the same non-server components that were installed during the previous Advanced Server installation. Please note that the new cluster and the old cluster must reside in different directories.

#### Step 2 - Empty the target database

The target cluster must not contain any data; you can create an empty cluster using the `initdb` command, or you can empty a database that was created during the installation of Advanced Server 9.6. If you have installed Advanced Server in PostgreSQL mode, the installer creates a single database named `postgres`; if you have installed Advanced Server in Oracle mode, it creates a database named `postgres` and a database named `edb`.

The easiest way to empty the target database is to drop the database and then create a new database. Before you invoke the `DROP DATABASE` command, you must disconnect any users or services that are currently using the database.

By default, the Advanced Server installation process installs and automatically starts the following services:

- `pgbouncer 1.7` - The PgBouncer service
- `edb-pgagent-9.6` - The pgAgent service

Before dropping the target database, halt any services that are included in your installation.

On Windows, navigate through the Control Panel to the Services manager; highlight each service in the Services list, and select Stop.

On Linux, open a terminal window, assume superuser privileges, and manually stop each service; for example, invoke the command:

```
service edb-pgagent-9.6 stop
```

to stop the pgAgent service.


After stopping any services that are currently connected to Advanced Server, you can use the EDB-PSQL command line client to drop and create a database. When the client opens, connect to the `template1` database as the database superuser; if prompted, provide authentication information. Then, use the following command to drop your database:

```
DROP DATABASE database_name;
```

Where *database\_name* is the name of the database.

Then, create an empty database based on the contents of the `template1` database (see Figure 8.1):

```
CREATE DATABASE database_name;
```



```
susan@localhost:/opt/edb/as9.6/bin
File Edit View Search Terminal Help
template1=# exit
[susan@localhost bin]$ ./psql -d template1 -U enterprisedb
Password for user enterprisedb:
psql.bin (9.6.1.4)
Type "help" for help.

template1=# DROP DATABASE edb;
DROP DATABASE
template1=# CREATE DATABASE edb;
CREATE DATABASE
template1=# █
```

Figure 8.1 - Creating an empty database in terminal.

### Step 3 - Set both servers in trust mode

During the upgrade process, `pg_upgrade` will connect to the old and new servers several times; to make the connection process easier, you can edit the `pg_hba.conf` file, setting the authentication mode to `trust`. To modify the `pg_hba.conf` file, navigate through the Start menu to the EDB Postgres menu; to the Advanced Server menu, and open the Expert Configuration menu; select the Edit `pg_hba.conf` menu option to open the `pg_hba.conf` file.

You should allow trust authentication for the previous Advanced Server installation, and Advanced Server 9.6 servers. Edit the `pg_hba.conf` file for both installations of Advanced Server as shown in Figure 8.2.




Figure 8.2 - Configuring Advanced Server to use trust authentication.

After editing each file, save the file and exit the editor.

If the system is required to maintain `md5` authentication mode during the upgrade process, you can specify user passwords for the database superuser in a password file (`pgpass.conf` on Windows, `.pgpass` on Linux). For more information about configuring a password file, see the PostgreSQL Core Documentation, available through:

<https://www.postgresql.org/docs/9.6/static/libpq-pgpass.html>

### Step 4 - Stop All Component Services and Servers

Before you invoke `pg_upgrade`, you must stop any services that belong to the original Advanced Server installation, Advanced Server 9.6 or the supporting components. This ensures that a service will not attempt to access either cluster during the upgrade process.



The services that are most likely to be running in your installation are:

Service:	On Linux:	On Windows
EnterpriseDB Postgres Advanced Server 9.6	edb-as-9.6	edb-as-9.6
Advanced Server 9.6 Scheduling Agent (pgAgent)	edb-pgagent-9.6	EnterpriseDB Postgres Advanced Server 9.6 Scheduling Agent
Infinite Cache 9.6	edb-icache	N/A
PgBouncer	Pgbouncer	pgbouncer
PgBouncer 1.6	ppas-pgbouncer-1.6 or ppas-pgbouncer16	ppas-pgbouncer-1.6
PgBouncer 1.7	edb-pgbouncer-1.7	edb-pgbouncer-1.7
PgPool	ppas-pgpool	N/A
PgPool 3.4	ppas-pgpool-3.4 or ppas-pgpool34 or	N/A
pgPool-II	edb-pgpool-3.5	N/A
Slony 9.6	edb-slony-replication-9.6	edb-slony-replication-9.6
xDB Subscription Server	edb-xdbsubserver-90	Subscription Service 90
xDB Subscription Server	edb-xdbsubserver-91	Subscription Service 91
EDB Replication Server v6.0	edb-xdbpubserver	Publication Service for xDB Replication Server
EDB Subscription Server v6.0	edb-xdbsubserver	Subscription Service for xDB Replication Server

### To stop a service on Windows:

Navigate through the Control Panel to the Services manager; highlight each running service displayed in the list, and select Stop.

### To stop a service on Linux:

Open a terminal window, assume superuser privileges, and manually stop each service at the command line. For example, the following command stops the `edbas-pgpool-3.5` service on a CentOS 6.x system:

```
/etc/init.d/edbas-pgpool-3.5 stop
```

### Step 5 for Linux only - Assume the identity of the cluster owner

If you are using Linux, assume the identity of the Advanced Server cluster owner. (The following example assumes Advanced Server was installed in the default, compatibility with Oracle database mode, thus assigning `enterprisedb` as the cluster owner. If installed in compatibility with PostgreSQL database mode, `postgres` is the cluster owner.)

```
su - enterprisedb
```

Enter the Advanced Server cluster owner password if prompted. Then, set the path to include the location of the `pg_upgrade` executable:

```
export PATH=$PATH:/opt/edb/as9.6/bin
```

During the upgrade process, `pg_upgrade` writes a file to the current working directory of the `enterprisedb` user; you must invoke `pg_upgrade` from a directory where the `enterprisedb` user has `write` privileges. After performing the above commands, navigate to a directory in which the `enterprisedb` user has sufficient privileges to write a file.

```
cd /tmp
```

Proceed to Step 6.

### Step 5 for Windows only - Assume the identity of the cluster owner

If you are using Windows, open a terminal window, assume the identity of the Advanced Server cluster owner and set the path to the `pg_upgrade` executable.

If the `--serviceaccount service_account_user` parameter was specified during the initial installation of Advanced Server, then `service_account_user` is the Advanced Server cluster owner and is the user to be given with the `RUNAS` command.

```
RUNAS /USER:service_account_user "CMD.EXE"  
SET PATH=%PATH%;C:\Program Files\edb\as9.6\bin
```

During the upgrade process, `pg_upgrade` writes a file to the current working directory of the service account user; you must invoke `pg_upgrade` from a directory where the service account user has `write` privileges. After performing the above commands, navigate to a directory in which the service account user has sufficient privileges to write a file.

```
cd %TEMP%
```

Proceed to Step 6.

If the `--serviceaccount` parameter was omitted during the initial installation of Advanced Server, then the default owner of the Advanced Server service and the database cluster is `NT AUTHORITY\NetworkService`.

When `NT AUTHORITY\NetworkService` is the service account user, the `RUNAS` command may not be usable as it prompts for a password and the `NT AUTHORITY\NetworkService` account is not assigned a password. Thus, there is typically a failure with an error message such as, “Unable to acquire user password”.

Under this circumstance a Windows utility program named `PsExec` must be used to run `CMD.EXE` as the service account `NT AUTHORITY\NetworkService`.

The `PsExec` program must be obtained by downloading `PsTools`, which is available at the following site:

<https://technet.microsoft.com/en-us/sysinternals/bb897553.aspx>

You can then use the following command to run `CMD.EXE` as `NT AUTHORITY\NetworkService`, and then set the path to the `pg_upgrade` executable.

```
psexec.exe -u "NT AUTHORITY\NetworkService" CMD.EXE
SET PATH=%PATH%;C:\Program Files\edb\as9.6\bin
```

During the upgrade process, `pg_upgrade` writes a file to the current working directory of the service account user; you must invoke `pg_upgrade` from a directory where the service account user has `write` privileges. After performing the above commands, navigate to a directory in which the service account user has sufficient privileges to write a file.

```
cd %TEMP%
```

Proceed with Step 6.

### Step 6 - Perform a consistency check

Before attempting an upgrade, perform a consistency check to assure that the old and new clusters are compatible and properly configured. Include the `--check` option to instruct `pg_upgrade` to perform the consistency check.

The following example demonstrates invoking `pg_upgrade` to perform a consistency check on Linux:

```
pg_upgrade -d /opt/PostgresPlus/9.5AS/data -D
/opt/edb/as9.6/data -U enterprisedb -b
/opt/PostgresPlus/9.5AS/bin -B /opt/edb/as9.6/bin -p 5444 -
P 5445 --check
```

If the command is successful, it will return `*Clusters are compatible*`.

If you are using Windows, you must quote any directory names that contain a space:

```
pg_upgrade.exe -d "C:\Program Files\ PostgresPlus\9.5AS
\data" -D "C:\Program Files\edb\as9.6\data" -U enterprisedb
-b "C:\Program Files\PostgresPlus\9.5AS\bin" -B
"C:\Program Files\edb\as9.6\bin" -p 5444 -P 5445 --check
```

During the consistency checking process, `pg_upgrade` will log any discrepancies that it finds to a file located in the directory from which `pg_upgrade` was invoked. When the consistency check completes, review the file to identify any missing components or upgrade conflicts. You must resolve any conflicts before invoking `pg_upgrade` to perform a version upgrade.

If `pg_upgrade` alerts you to a missing component, you can use StackBuilder Plus to add the component that contains the component. Before using StackBuilder Plus, you must restart the Advanced Server 9.6 service. After restarting the service, open StackBuilder Plus by navigating through the Start menu to the Advanced Server 9.6 menu, and selecting StackBuilder Plus. Follow the onscreen advice of the StackBuilder Plus wizard to download and install the missing components.

For more information about using StackBuilder Plus, please see Section [4.5, Using StackBuilder Plus](#).

When `pg_upgrade` has confirmed that the clusters are compatible, you can perform a version upgrade.

### Step 7 - Run `pg_upgrade`

After confirming that the clusters are compatible, you can invoke `pg_upgrade` to upgrade the old cluster to the new version of Advanced Server.

On Linux:

```
pg_upgrade -d /opt/PostgresPlus/9.5AS/data -D
/opt/edb/as9.6/data -U enterprisedb -b
/opt/PostgresPlus/9.5AS/bin -B /opt/edb/as9.6/bin -p 5444 -
P 5445
```

On Windows:

```
pg_upgrade.exe -d "C:\Program
Files\PostgresPlus\9.5AS\data"
-D "C:\Program Files\edb\as9.6\data" -U enterprisedb
-b "C:\Program Files\PostgresPlus\9.5AS\bin" -B
"C:\Program Files\edb\as9.6\bin" -p 5444 -P 5445
```

`pg_upgrade` will display the progress of the upgrade onscreen:

```
$ pg_upgrade -d /opt/edb/as9.6/data -D /opt/edb/as9.6/data -U enterprisedb -b
/opt/edb/as9.6/bin -B /opt/edb/as9.6/bin -p 5444 -P 5445
Performing Consistency Checks
-----
Checking current, bin, and data directories          ok
Checking cluster versions                          ok
Checking database user is a superuser              ok
Checking for prepared transactions                 ok
```

```

Checking for reg* system OID user data types           ok
Checking for contrib/isn with bigint-passing mismatch ok
Creating catalog dump                                 ok
Checking for presence of required libraries           ok
Checking database user is a superuser                ok
Checking for prepared transactions                    ok

If pg_upgrade fails after this point, you must re-initdb the
new cluster before continuing.

Performing Upgrade
-----
Analyzing all rows in the new cluster                 ok
Freezing all rows on the new cluster                 ok
Deleting files from new pg_clog                       ok
Copying old pg_clog to new server                    ok
Setting next transaction ID for new cluster           ok
Resetting WAL archives                               ok
Setting frozenxid counters in new cluster            ok
Creating databases in the new cluster                ok
Adding support functions to new cluster              ok
Restoring database schema to new cluster             ok
Removing support functions from new cluster           ok
Copying user relation files                          ok

Setting next OID for new cluster                      ok
Creating script to analyze new cluster               ok
Creating script to delete old cluster                ok

Upgrade Complete
-----
Optimizer statistics are not transferred by pg_upgrade so,
once you start the new server, consider running:
    analyze_new_cluster.sh

Running this script will delete the old cluster's data files:
    delete_old_cluster.sh

```

While `pg_upgrade` runs, it may generate SQL scripts that handle special circumstances that it has encountered during your upgrade. For example, if the old cluster contains large objects, you may need to invoke a script that defines the default permissions for the objects in the new cluster. When performing the pre-upgrade consistency check `pg_upgrade` will alert you to any script that you may be required to run manually.

You must invoke the scripts after `pg_upgrade` completes. To invoke the scripts, connect to the new cluster as a database superuser with the EDB-PSQL command line client, and invoke each script using the `\i` option:

```
\i complete_path_to_script/script.sql
```

It is generally unsafe to access tables referenced in rebuild scripts until the rebuild scripts have completed; accessing the tables could yield incorrect results or poor performance. Tables not referenced in rebuild scripts can be accessed immediately.

**Note:** If `pg_upgrade` fails to complete the upgrade process, the old cluster will be unchanged, except that `$PGDATA/global/pg_control` is renamed to

`pg_control.old` and each tablespace is renamed to `tablespace.old`. To revert to the pre-invocation state:

- Delete any tablespace directories created by the new cluster.
- Rename `$PGDATA/global/pg_control`, removing the `.old` suffix.
- Rename the old cluster tablespace directory names, removing the `.old` suffix.
- Remove any database objects (from the new cluster) that may have been moved before the upgrade failed.

After performing these steps, resolve any upgrade conflicts encountered before attempting the upgrade again.

When the upgrade is complete, `pg_upgrade` may also recommend vacuuming the new cluster, and will provide a script that allows you to delete the old cluster.

*Before removing the old cluster, ensure that the cluster has been upgraded as expected, and that you have preserved a backup of the cluster in case you need to revert to a previous version.*

### **Step 8 - Restore the authentication settings in the `pg_hba.conf` file**

If you modified the `pg_hba.conf` file to permit `trust` authentication, update the contents of the `pg_hba.conf` file to reflect your preferred authentication settings.

### **Step 9 - Move and identify user-defined tablespaces (*Optional*)**

If you have data stored in a user-defined tablespace, you must manually relocate tablespace files after upgrading; move the files to the new location and update the symbolic links (located in the `pg_tblspc` directory under your cluster's `data` directory) to point to the files.

## 8.4 *pg\_upgrade* Troubleshooting

The troubleshooting tips in this section address problems you may encounter when using *pg\_upgrade*.

### 8.4.1 Upgrade Error - There seems to be a postmaster servicing the cluster

If *pg\_upgrade* reports that a postmaster is servicing the cluster, please stop all Advanced Server services and try the upgrade again. See Step 4 in Section [8.3, \*Upgrading to Advanced Server 9.6\*](#) for detailed information about stopping a service.

### 8.4.2 Upgrade Error - *fe\_sendauth: no password supplied*

If *pg\_upgrade* reports an authentication error that references a missing password, please modify the *pg\_hba.conf* files in the old and new cluster to enable `trust` authentication, or configure the system to use a *pgpass.conf* file. See Step 3 in Section [8.3, \*Upgrading to Advanced Server 9.6\*](#) for detailed information about editing the *pg\_hba.conf* file.

### 8.4.3 Upgrade Error - New cluster is not empty; exiting

If *pg\_upgrade* reports that the new cluster is not empty, please empty the new cluster. For details about providing an empty target cluster, see Step 2 in Section [8.3, \*Upgrading to Advanced Server 9.6\*](#). **Please note:** the target cluster may not contain any user-defined databases.

### 8.4.4 Upgrade Error - Failed to load library

If the original Advanced Server cluster included libraries that are not included in the Advanced Server 9.6 cluster, `pg_upgrade` will alert you to the missing component during the consistency check by writing an entry to the `loadable_libraries.txt` file in the directory from which you invoked `pg_upgrade`.

In the example shown, the old cluster contains PostGIS, while the new installation does not. Generally, for missing libraries that are not part of a major component upgrade, perform the following steps:

- Restart the Advanced Server service.

Use StackBuilder Plus to download and install the missing module as described in Chapter 4, *Using StackBuilder Plus*.

- Stop the Advanced Server service.
- Resume the upgrade process: invoke `pg_upgrade` to perform consistency checking.
- When you have resolved any remaining problems noted in the consistency checks, invoke `pg_upgrade` to perform the data migration from the old cluster to the new cluster.

Please Note: Advanced Server (version 9.2 and later) is compatible with PostGIS 2.3. For detailed instructions about upgrading to PostGIS 2.3, see Section [7.13.1](#).

## 8.5 Reverting to the Old Cluster

The method used to revert to a previous cluster varies with the options specified when invoking `pg_upgrade`:

- If you specified the `--check` option when invoking `pg_upgrade`, an upgrade has not been performed, and no modifications have been made to the old cluster; you can re-use the old cluster at any time.
- If you included the `--link` option when invoking `pg_upgrade`, the data files are shared between the old and new cluster after the upgrade completes. If you have started the server that is servicing the new cluster, the new server has written to those shared files and it is unsafe to use the old cluster.



- If you ran `pg_upgrade` without the `--link` specification or have not started the new server, the old cluster is unchanged, except that the `.old` suffix has been appended to the `$PGDATA/global/pg_control` and `tablespace` directories.
- To reuse the old cluster, delete the `tablespace` directories created by the new cluster and remove the `.old` suffix from `$PGDATA/global/pg_control` and the old cluster `tablespace` directory names and restart the server that services the old cluster.

## 8.6 Migration to Version 9.6

A dump/restore using `pg_dumpall` or use of `pg_upgrade` is required for those wishing to migrate data from any previous release. See Section **Error! Reference source not found.**, *Upgrading an Installation With `pg_upgrade`* for general information on migrating to new major releases.

Version 9.6 contains a number of changes that may affect compatibility with previous releases. Observe the following incompatibilities:

- Improve the `pg_stat_activity` view's information about what a process is waiting for.

Historically a process has only been shown as waiting if it was waiting for a heavyweight lock. Now waits for lightweight locks and buffer pins are also shown in `pg_stat_activity`. Also, the type of lock being waited for is now visible. These changes replace the `waiting` column with `wait_event_type` and `wait_event`.

- In `to_char()`, do not count a minus sign (when needed) as part of the field width for time-related fields.

For example, `to_char('-4 years'::interval, 'YY')` now returns `-04`, rather than `-4`.

- Make `extract()` behave more reasonably with infinite inputs.

Historically the `extract()` function just returned zero given an infinite timestamp, regardless of the given field name. Make it return `infinity` or `-infinity` as appropriate when the requested field is one that is monotonically

increasing (e.g, `year`, `epoch`), or `NULL` when it is not (e.g., `day`, `hour`). Also, throw the expected error for bad field names.

- Remove PL/pgSQL's "feature" that suppressed the innermost line of `CONTEXT` for messages emitted by `RAISE` commands.

This ancient backwards-compatibility hack was agreed to have outlived its usefulness.

- Fix the default text search parser to allow leading digits in `email` and host tokens.

In most cases this will result in few changes in the parsing of text. But if you have data where such addresses occur frequently, it may be worth rebuilding dependent `tsvector` columns and indexes so that addresses of this form will be found properly by text searches.

- Extend contrib/unaccent's standard `unaccent.rules` file to handle all diacritics known to Unicode, and to expand ligatures correctly.

The previous version neglected to convert some less-common letters with diacritic marks. Also, ligatures are now expanded into separate letters. Installations that use this rules file may wish to rebuild `tsvector` columns and indexes that depend on the result.

- Remove the long-deprecated `CREATEUSER/NOCREATEUSER` options from `CREATE ROLE` and allied commands.

`CREATEUSER` actually meant `SUPERUSER`, for ancient backwards-compatibility reasons. This has been a constant source of confusion for people who (reasonably) expect it to mean `CREATEROLE`. It has been deprecated for ten years now, so fix the problem by removing it.

- Treat role names beginning with `pg_` as reserved.

User creation of such role names is now disallowed. This prevents conflicts with built-in roles created by `initdb`.

- Change a column name in the `information_schema.routines` view from `result_cast_character_set_name` to `result_cast_char_set_name`.

The SQL:2011 standard specifies the longer name, but that appears to be a mistake, because adjacent column names use the shorter style, as do other `information_schema` views.

- `psql`'s `-c` option no longer implies `--no-psqlrc`.

Write `--no-psqlrc` (or its abbreviation `-X`) explicitly to obtain the old behavior. Scripts so modified will still work with old versions of `psql`.

- Improve `pg_restore`'s `-t` option to match all types of relations, not only plain tables.
- Change the display format used for `NextXID` in `pg_controldata` and related places.

Display epoch-and-transaction-ID values in the format `number:number`. The previous format `number/number` was confusingly similar to that used for LSNs.

- Update extension functions to be marked parallel-safe where appropriate.

Many of the standard extensions have been updated to allow their functions to be executed within parallel query worker processes. These changes will not take effect in databases `pg_upgrade'd` from prior versions unless you apply `ALTER EXTENSION UPDATE` to each such extension (in each database of a cluster).

# 9 Uninstalling Advanced Server

Note that after uninstalling Advanced Server, the cluster data files remain intact and the service user persists. You may manually remove the cluster data and service user from the system.

## 9.1 Uninstalling a RPM Package

You can use either the `rpm` or `yum` command to remove RPM packages. Note that removing a package does not damage the Advanced Server `data` directory.

### 9.1.1 Uninstalling a RPM Package with rpm

Include the `-e` option on the `rpm` command to remove installed packages; the command syntax is:

```
rpm -e package_name [package_name...]
```

Where `package_name` is the name of the package that you would like to remove. The package name is the name of the `.rpm` file used when installing the package, with the version number and file extension (`.rpm`) removed; for example, the command:

```
rpm -e edb-as96
```

Removes the package installed with the command:

```
rpm -i edb-as96-9.6-x.rhel6.rpm
```

To instruct `rpm` to remove multiple packages, provide a list of packages you wish to remove when invoking the command.

### 9.1.2 Uninstalling a RPM Package with yum

You can use the `yum remove` command to remove an RPM package. To remove a package, open a terminal window, assume superuser privileges, and enter the command:

```
yum remove package_name
```

Where `package_name` is the name of the package that you would like to remove. The package name is the name of the `.rpm` file used when installing the package, with the file extension (`.rpm`) removed; for example, the command:

```
yum remove edb-as96
```

Removes the package installed with the command:

```
yum install edb-as96-9.6.x.x.rhel6.rpm
```

**Note:** yum and RPM will not remove a package that is required by another package. If you attempt to remove a package that satisfies a package dependency, yum or RPM will provide a warning.

## 9.2 Using Advanced Server Uninstallers at the Command Line

The Advanced Server interactive installer creates uninstallers that you can use to remove Advanced Server or any of its individual components. If you uninstall an Advanced Server component, the remainder of the Advanced Server installation will remain intact.

The following table lists the names and locations of the Advanced Server binary uninstallers on Linux:

Advanced Server Component	Uninstaller Name	Linux Uninstaller Location
The Database Server	uninstall-edb-as96-dbserver	/opt/edb/as9.6
Advanced Server and all supporting modules	uninstall-edb-as96-meta	/opt/edb
Connectors	uninstall-edb-connectors	/opt/edb/connectors
EDB*Plus	uninstall-edb-as96-edbplus	/opt/edb/as9.6/edbplus
Infinite Cache	uninstall_edb_infinitecache	/opt/edb/as9.6/share/contrib
Migration Toolkit	uninstall-edb-migrationtoolkit	/opt/edb/mtk
pgAdmin 4	uninstall-pgadmin4	/opt/edb/pgadmin4
pgAgent	uninstall-edb-as96-pgagent	/opt/edb/as9.6
PgBouncer 1.7	uninstall-edb-pgbouncer	/opt/edb/pgbouncer1.7
pgPool-II	uninstall-edb-pgpool	/opt/edb/pgpool3.5
pgPool-II Extension	uninstall-pgpool_extension	/opt/edb/as9.6
Slony Replication	uninstall-replication	/opt/edb/as9.6
StackBuilder Plus	uninstall-edb-stackbuilderplus	/opt/edb/sbp

The following table lists the names and locations of the Advanced Server binary uninstallers on Windows:

Advanced Server Component	Uninstaller Name	Windows Uninstaller Location
The Database Server	uninstall-edb-as96-dbserver	C:\Program Files\edb\as9.6
Advanced Server and all supporting modules	uninstall-edb-as96-meta	C:\Program Files\edb
Connectors	uninstall-edb-connectors	C:\Program Files\edb\connectors
EDB*Plus	uninstall-edb-as96-edbplus	C:\Program Files\edb\as9.6\edbplus
Migration Toolkit	uninstall-edb-migrationtoolkit	C:\Program Files\edb\mtk
pgAdmin 4	uninstall-ppadmin4	C:\Program Files\edb\pgadmin4
pgAgent	uninstall-edb-as96-pgagent	C:\Program Files\edb\as9.6
PgBouncer 1.7	uninstall-edb-pgbouncer	C:\Program Files\edb\pgbouncer1.7
PL/Java	pljava_uninstall	C:\Program Files\edb\as9.6\share
Slony Replication	uninstall-replication	C:\Program Files\edb\as9.6
StackBuilder Plus	uninstall-edb-stackbuilderplus	C:\Program Files\edb\sbp
xDB Replication Server	uninstall-xdbreplicationserver	C:\Program Files (x86)\PostgreSQL\EnterpriseDB-xDBReplicationServer

To uninstall Advanced Server and all of the supporting modules, navigate to the `Advanced Server` directory and enter:


On Linux, assume superuser privileges and enter:

```
./uninstall-edb-as96-meta
```

On Windows assume Administrator privileges and enter:


```
uninstall-edb-as96-meta
```

A dialog opens, asking you to confirm your decision to uninstall Advanced Server (see Figure 9.1)




*Figure 9.1 - A dialog confirms that you wish to uninstall Advanced Server.*

Click `Yes` to confirm that you wish to uninstall Advanced Server. As the uninstallation progresses, a dialog displays a progress indicator for each uninstalled module. When the un-installer completes, a popup confirms that the data directory and service account have not been removed (see Figure 9.2).



*Figure 9.2 - A dialog confirms that the data directory and service user have not been removed.*

When the uninstallation is complete, an `Info` dialog opens to confirm that Advanced Server (and/or its components) has been removed (see Figure 9.3).



*Figure 9.3 - The uninstallation is complete.*



### 9.3 Uninstalling Advanced Server on a Windows System

This section describes how to use the uninstaller to remove Advanced Server and all of its components. The following steps are easily adapted to remove a single service. Note that a system restart may be required to complete the removal of some Advanced Server components; if prompted, click **OK** to continue.

You can use the graphical interface provided by Windows to uninstall Advanced Server 9.6. Navigate through the Windows Control Panel to open the Windows Programs and Features dialog (shown in Figure 9.4).






Figure 9.4 - The Programs and Features dialog.

Right click **EDB Postgres Advanced Server 9.6 (Complete)** and select **Uninstall/Change** from the context menu to uninstall Advanced Server and all supporting Advanced Server components; optionally, right click on the Advanced Server component you wish to uninstall. If you are removing both the server and its supporting modules, a popup (shown in Figure 9.5) will prompt you to confirm that you wish to remove Advanced Server and its supporting components.




*Figure 9.5 - A dialog asks you to confirm that you wish to remove the server and its components.*

Please note that uninstalling Advanced Server will leave the data directory and database service user intact; you will be prompted for a confirmation (as shown in Figure 9.6).



*Figure 9.6 - A popup confirms that the data directory and service user account have not been removed from the host system.*

Popup dialogs signal the removal of each Advanced Server component. When the uninstallation process is complete, an `Info` dialog opens to confirm (shown in Figure 9.7)



*Figure 9.7 - An Info dialog confirms the uninstallation.*